

DIPLOMADO DE PROFUNDIZACION CISCO
PRUEBA DE HABILIDADES PRÁCTICAS CCNP

JONATHAN ALBERTO GOMEZ

UNIVERSIDAD NACIONAL ABIERTA Y A DISTANCIA - UNAD
ESCUELA DE CIENCIAS BÁSICAS, TECNOLOGÍA E INGENIERÍA -
EBCBTI
INGENIERÍA DE TELECOMUNICACIONES
BOGOTA D.C
2022

DIPLOMADO DE PROFUNDIZACION CISCO
PRUEBA DE HABILIDADES PRÁCTICAS CCNP

JONATHAN ALBERTO GOMEZ

Diplomado de opción de grado presentado para
optar el título de INGENIERO DE
TELECOMUNICACIONES

DIRECTOR:
JHON HAROLD PEREZ CALDERON

UNIVERSIDAD NACIONAL ABIERTA Y A DISTANCIA - UNAD
ESCUELA DE CIENCIAS BÁSICAS, TECNOLOGÍA E INGENIERÍA -
ECBTI
INGENIERÍA DE TELECOMUNICACIONES
BOGOTA D.C
2022

NOTA DE ACEPTACIÓN

Firma del Presidente del Jurado

Firma del Jurado

Firma del Jurado

BOGOTA D.C, 02 de diciembre de 2022

AGRADECIMIENTOS

Este esfuerzo lo dedico a mi familia, a mis padres y hermana por su apoyo incondicional e incansable para hoy poder llegar a un logro más, agradecimientos a los instructores de la Universidad Nacional Abierta y a Distancia – UNAD por sus esfuerzos, conocimiento y guía académica para ser de nosotros profesionales íntegros que podamos aportar positivamente al desarrollo de nuestras comunidades y país, igualmente agradecer a la universidad por la modalidad de estudios virtuales implementada ya que presentan gran oportunidad a muchas personas que poseen dificultades para acceder a educación presencial.

CONTENIDO

AGRADECIMIENTOS	4
CONTENIDO	5
LISTA DE TABLAS	6
LISTA DE FIGURAS	7
GLOSARIO	8
RESUMEN	9
ABSTRACT	9
INTRODUCCIÓN	10
DESARROLLO	11
1. Escenario 1	11
2. Escenario 2	38
CONCLUSIONES	59
BIBLIOGRÁFIA	60

LISTA DE TABLAS

Tabla 1. Addressing Table -----	12
Tabla 2. Configuración de la red de capa 2 y la compatibilidad con el host -----	27

LISTA DE FIGURAS

Figura 1. Simulación escenario 1 -----	11
Figura 2. Configuración Router R1 -----	15
Figura 3. Configuración Router R2 -----	17
Figura 4. Configuración Router R3 -----	18
Figura 5. Configuración Switch D1 -----	21
Figura 6. Configuración Switch D2 -----	23
Figura 7. Configuración Switch A1 -----	24
Figura 8. Configuración PC1 -----	25
Figura 9. Configuración PC2 -----	25
Figura 10. Configuración Switch D1 Tarea 2.1 – 2.6 -----	28
Figura 11. Verificación Configuración Switch D1 Tarea 2.1 – 2.6 -----	29
Figura 12. Configuración Switch D2 Tarea 2.1 – 2.6 -----	30
Figura 13. Verificación Configuración Switch D2 Tarea 2.1 – 2.6 -----	31
Figura 14. Configuración Switch A1 Tarea 2.1 – 2.6 -----	33
Figura 15. Verificación Configuración Switch D2 Tarea 2.1 – 2.6 -----	34
Figura 16. Verificación conectividad LAN local PC1 -----	35
Figura 17. Verificación conectividad LAN local PC2 -----	36
Figura 18. Verificación conectividad LAN local PC3 -----	37
Figura 19. Verificación conectividad LAN local PC4 -----	38
Figura 20. Configuración protocolos de enrutamiento R1 Task 3.1 – 3.4 -----	42
Figura 21. Configuración protocolos de enrutamiento R2 Task 3.1 – 3.4 -----	43
Figura 22. Configuración protocolos de enrutamiento R3 Task 3.1 – 3.4 -----	44
Figura 23. Configuración protocolos de enrutamiento Switch D1 Task 3.1 – 3.4 -----	46
Figura 24. Configuración protocolos de enrutamiento Switch D2 Task 3.1 – 3.4 -----	48
Figura 25. Configurar la redundancia del primer salto Switch D1 Task 4.1 – 4.4 -----	54
Figura 26. Verificación configurar la redundancia del primer salto Switch D1 Task 4.1 - 4.4 -----	55
Figura 27. Configurar la redundancia del primer salto Switch D2 Task 4.1 – 4.4 -----	57
Figura 28. Verificación configurar la redundancia del primer salto Switch D1 Task 4.1 - 4.4 -----	58

GLOSARIO

NETWORKING: El término hacer contactos, o el anglicismo *networking*, se usa en el mundo de los negocios para hacer referencia a una actividad socio económica en la que profesionales y emprendedores se reúnen para formar relaciones empresariales, crear y desarrollar oportunidades de negocio, compartir información y buscar clientes potenciales.

LOOPBACK: La dirección de *loopback* es una dirección especial que los hosts utilizan para dirigir el tráfico hacia ellos mismos. La dirección de *loopback* crea un método de acceso directo para las aplicaciones y servicios TCP/IP que se ejecutan en el mismo dispositivo para comunicarse entre sí. Al utilizar la dirección de *loopback*, en lugar de la dirección host IPv4 asignada, dos servicios en el mismo host pueden desviar las capas inferiores del stack de TCP/IP. También es posible hacer ping a la dirección de *loopback* para probar la configuración de TCP/IP en el host local.

PING: Como programa, ping es una utilidad de diagnóstico en redes de computadoras que comprueba el estado de la comunicación del anfitrión local con uno o varios equipos remotos de una red que ejecuten IP. Se vale del envío de paquetes ICMP de solicitud (*ICMP Echo Request*) y de respuesta (*ICMP Echo Reply*). Mediante esta utilidad puede diagnosticarse el estado, velocidad y calidad de una red determinada.

CCNP: Certificación de enrutamiento y commutación CCNP.

La certificación de enrutamiento y commutación Cisco Certified Network Professional(CCNP) valida la capacidad de planificar, implementar, verificar y solucionar problemas de redes empresariales locales y de área amplia y trabajar en colaboración con especialistas en soluciones avanzadas de seguridad, voz, inalámbrica y video.

VLAN: Una VLAN, acrónimo de virtual LAN (red de área local virtual), es un método para crear redes lógicas independientes dentro de una misma red física. Varias VLAN pueden coexistir en un único commutador físico o en una única red física. Son útiles para reducir el dominio de difusión y ayudan en la administración de la red, separando segmentos lógicos de una red de área local (los departamentos de una empresa, por ejemplo) que no deberían intercambiar datos usando la red local (aunque podrían hacerlo a través de un enrutador o un commutador de capa OSI 3 y 4).

RESUMEN

Este trabajo tiene como objetivo desarrollar la prueba de habilidades prácticas que es una herramienta de evaluación del Diplomado de profundización de Cisco CCNP, con la cual se busca medir las habilidades y competencias que el estudiante logró alcanzar mediante el desarrollo del diplomado y cada una de sus actividades.

Esta actividad final contara con dos escenarios en la cual cada estudiante realizará cada una de las configuraciones necesarias, apoyándose en los conocimientos adquiridos en conmutación, enrutamiento, redes y electrónica para dar solución a los dos problemas planteados, el estudiante contara con el apoyo de software especializado y pondrá en ejecución lo aprendido en el transcurso del curso.

Palabras Clave: CISCO, CCNP, Comutación, Enrutamiento, Redes, Electrónica.

ABSTRACT

This work aims to develop the practical skills test, which is an evaluation tool of the Cisco CCNP Deepening Diploma, which seeks to measure the skills and competences that the student achieved through the development of the diploma and each of its activities.

This final activity will have two scenarios in which each student will perform each of the necessary configurations, relying on the knowledge acquired in switching, routing, network design and electronics to solve the two problems posed, the student will have the support of specialized software and will implement what has been learned during the course.

Keywords: CISCO, CCNP, Routing, Switching, Networking, Electronics.

INTRODUCCIÓN

Este trabajo presenta el desarroellar de la prueba de habilidades prácticas la cual es una herramienta de evaluación del Diplomado de profundización Cisco CCNP, para optar el título de ingeniero. El desarrollo de esta actividad se llevará a cabo poniendo en práctica los conocimientos tanto teóricos y prácticos adquiridos a lo largo del curso. Empleando la metodología adquirida a lo largo del diplomado la cual consistió en estudiar y entender la parte teórica para luego llevarla a la práctica mediremos nuestro conocimiento mediante la solución de dos problemas que abarcan el diseño, implementación y configuración de redes de datos, protocolos de enrutamiento, programación, normas preparándonos e instruyéndonos para que seamos capaces de asumir retos en nuestra vida laboral y profesional, la cual como futuro ingeniero de Telecomunicaciones poder aplicar estos conocimientos en la transformación, mejoramiento y expansión de redes de nueva generación y de la tecnología que nos rodea.

En el primer escenario se desarrollará la evaluación de habilidades ENCOR, donde tiene como primer objetivo construir una red y configurar los ajustes básicos del dispositivo y direccionamiento de la interfaz, el segundo objetivo es configurar la red de capa 2 y la compatibilidad con el host, seguido del tercer objetivo configurar protocolos de enrutamiento y como cuarto objetivo configurar la redundancia del primer salto.

En esta evaluación de habilidades, se tiene la responsabilidad completar la configuración de la red para que haya accesibilidad completa de extremo a extremo, para que los hosts tengan soporte de puerta de enlace predeterminada confiable y para que los protocolos de administración estén operativos dentro de la parte de "Red de la empresa" de la topología.

Se debe verificar que las configuraciones cumplan con las especificaciones proporcionadas y que los dispositivos funcionen según lo requerido. Los enrutadores utilizados con los laboratorios prácticos de CCNP son enrutadores Cisco 7200. Los conmutadores utilizados en las prácticas de laboratorio son conmutadores Cisco Catalyst L2.

El segundo escenario se desarrollará la evaluación de habilidades ENCOR continuación Escenario 1, la cual consiste en configurar protocolos de enrutamiento IPv4 e IPv6. Al final de esta parte, la red debe estar completamente convergente. Los pings de IPv4 e IPv6 a la interfaz Loopback 0 desde D1 y D2 deberían ser exitosos.

DESARROLLO

1. ESCENARIO 1

ENCOR Skills Assessment (Scenario 1)

Topology




Figura 1. Simulación escenario 1

Addressing Table

Device	Interface	IPv4 Address	Ipv6 Address	Ipv6 Link-Local
R1	E1/0	209.165.200.225/27	2001:db8:200::1/64	fe80::1:1
	E1/2	10.27.10.1/24	2001:db8:100:1010::1/64	fe80::1:2
	E1/1	10.27.13.1/24	2001:db8:100:1013::1/64	fe80::1:3
R2	E1/0	209.165.200.226/27	2001:db8:200::2/64	fe80::2:1
	Loopback0	2.2.2.2/32	2001:db8:2222::1/128	fe80::2:3
R3	E1/0	10.27.11.1/24	2001:db8:100:1011::1/64	fe80::3:2
	E1/1	10.27.13.3/24	2001:db8:100:1013::3/64	fe80::3:3
D1	E1/2	10.27.10.2/24	2001:db8:100:1010::2/64	fe80::d1:1
	VLAN 100	10.27.100.1/24	2001:db8:100:100::1/64	fe80::d1:2
	VLAN 101	10.27.101.1/24	2001:db8:100:101::1/64	fe80::d1:3
	VLAN 102	10.27.102.1/24	2001:db8:100:102::1/64	fe80::d1:4
D2	E1/0	10.27.11.2/24	2001:db8:100:1011::2/64	fe80::d2:1
	VLAN 100	10.27.100.2/24	2001:db8:100:100::2/64	fe80::d2:2
	VLAN 101	10.27.101.2/24	2001:db8:100:101::2/64	fe80::d2:3
	VLAN 102	10.27.102.2/24	2001:db8:100:102::2/64	fe80::d2:4
A1	VLAN 100	10.27.100.3/23	2001:db8:100:100::3/64	fe80::a1:1
PC1	NIC	10.27.100.5/24	2001:db8:100:100::5/64	EUI-64
PC2	NIC	DHCP	SLAAC	EUI-64
PC3	NIC	DHCP	SLAAC	EUI-64
PC4	NIC	10.27.100.6/24	2001:db8:100:100::6/64	EUI-64

Tabla 1. Addressing Table

Objectives

- Part 1: Build the Network and Configure Basic Device Settings and Interface Addressing**
- Part 2: Configure the Layer 2 Network and Host Support**
- Part 3: Configure Routing Protocols**
- Part 4: Configure First-Hop Redundancy**

Background / Scenario

In this skills assessment, you are responsible for completing the configuration of the network so there is full end-to-end reachability, so the hosts have reliable default gateway support, and so that management protocols are operational within the “Company Network” part of the topology. Be careful to verify that your configurations meet the provided specifications and that the devices perform as required.


Note: The routers used with CCNP hands-on labs are Cisco 7200 routers. The switches used in the labs are Cisco Catalyst L2 switches. Other routers, switches, and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and the output produced might vary from what is shown in the labs.

Note: Make sure that the switches have been erased and have no startup configurations. If you are unsure, contact your instructor.


Note: The letters "X, Y" represent the last two digits of your ID number (cédula). Para mi caso mi cedula es (1032422827), últimos dos numero son(27)

Required Resources

- 3 Routers (Cisco 7200). [Click on the download link of the images for GNS3.](#)
- 3 Switches (Cisco IOU L2). [Click on the download link of the images for GNS3.](#)
- 4 PCs (Use the GNS3's VPCS)
- After the configuration of devices in GNS3, the Slots of the network adapters of the SW must be configured as follows:



And of the Routers like this:



Part 1: Build the Network and Configure Basic Device Settings and Interface Addressing

In Part 1, you will set up the network topology and configure basic settings and interface addressing.

Step 1: Cable the network as shown in the topology.

Attach the devices as shown in the topology diagram, and cable as necessary.

Step 2: Configure basic settings for each device.

- a. Console into each device, enter global configuration mode, and apply the basic settings. The startup configurations for each device are provided below.


Router R1

```
hostname R1
ipv6 unicast-routing
no ip domain lookup
banner motd # R1, ENCOR Skills Assessment#
line con 0
exec-timeout 0 0
logging synchronous
exit
interface e1/0
ip address 209.165.200.225 255.255.255.224
ipv6 address fe80::1:1 link-local
ipv6 address 2001:db8:200::1/64
no shutdown
exit
interface e1/2
ip address 10.27.10.1 255.255.255.0
ipv6 address fe80::1:2 link-local
ipv6 address 2001:db8:100:1010::1/64
no shutdown
exit
interface e1/1
ip address 10.XY.13.1 255.255.255.0
ipv6 address fe80::1:3 link-local
ipv6 address 2001:db8:100:1013::1/64
no shutdown
exit
```

```

Nov 19 20:43:07.427: %LINK-5-CHANGED: Interface Ethernet1/0, changed state to a
dministratively down
Nov 19 20:43:07.435: %LINK-5-CHANGED: Interface Ethernet1/1, changed state to a
dministratively down
Nov 19 20:43:07.447: %LINK-5-CHANGED: Interface Ethernet1/2, changed state to a
dministratively down
Nov 19 20:43:07.455: %LINK-5-CHANGED: Interface Ethernet1/3, changed state to a
dministratively down
Nov 19 20:43:07.455: %LINK-5-CHANGED: Interface Ethernet2/0, changed state to a
dministratively down
Nov 19 20:43:07.455: %LINK-5-CHANGED: Interface Ethernet2/1, changed state to a
dministratively down
Nov 19 20:43:07.455: %LINK-5-CHANGED: Interface Ethernet2/2, changed state to a
dministratively down
Nov 19 20:43:07.455: %LINK-5-CHANGED: Interface Ethernet2/3, changed state to a
dministratively down
R1#
R1enable
R1configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#hostname R1
R1(config)#ipv6 unicast-routing
R1(config)#no ip domain lookup
R1(config)#banner motd # R1, ENCOR Skills Assessment#
R1(config)#line con 0
R1(config-line)# exec-timeout 0 0
R1(config-line)# logging synchronous
R1(config-line)exit
R1(config)#interface e1/0
R1(config-if)# ip address 209.165.200.225 255.255.255.224
R1(config-if)# ipv6 address fe80::1:111 link-local
R1(config-if)# ipv6 address 2001:db8:200::1/64
R1(config-if)# no shutdown
R1(config-if)# exit
R1(config)#interface e1/1
R1(config-if)# ip address 10.XY.13.1 255.255.255.0
R1(config-if)^
% Invalid input detected at '^' marker.
R1(config-if)# ipv6 address fe80::1:112 link-local
R1(config-if)# ipv6 address 2001:db8:100:1010::1/64
R1(config-if)# no shutdown
R1(config-if)# exit
R1(config)#
R1(config)#
Nov 19 20:44:05.275: %LINK-3-UPDOWN: Interface Ethernet1/0, changed state to up
Nov 19 20:44:05.527: %LINK-3-UPDOWN: Interface Ethernet1/2, changed state to up
Nov 19 20:44:05.690: %LINK-3-UPDOWN: Interface Ethernet1/1, changed state to up
Nov 19 20:44:06.275: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/0, changed state to up
R1(config)#
Nov 19 20:44:06.527: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/2, changed state to up
Nov 19 20:44:06.699: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/1, changed state to up
R1(config)#
R1(config)#
Nov 19 20:44:16.343: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not half duplex), with D1 Ethernet1/2 (half duplex).
R1(config)#

```

solarwinds  | Solar-PuTTY *free tool* © 2019 SolarWind

13°C ^ ☰ 🖥 🔊 ESP 8:44 p. m. 19/11/2022
 

Figura 2. Configuración Router R1

Router R2

```

hostname R2
ipv6 unicast-routing
no ip domain lookup
banner motd # R2, ENCOR Skills Assessment#
line con 0
exec-timeout 0 0
logging synchronous
exit
interface e1/0
ip address 209.165.200.226 255.255.255.224

```

```

ipv6 address fe80::2:1 link-local
ipv6 address 2001:db8:200::2/64
no shutdown
exit
interface Loopback 0
ip address 2.2.2.2 255.255.255.255
ipv6 address fe80::2:3 link-local
ipv6 address 2001:db8:2222::1/128
no shutdown
exit

```

```

Nov 19 20:43:10.231: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/0, changed state to down
Nov 19 20:43:10.231: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/0, changed state to down
Nov 19 20:43:10.231: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/1, changed state to down
Nov 19 20:43:10.231: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/2, changed state to down
Nov 19 20:43:10.231: %LINK-5-CHANGED: Interface FastEthernet0/0, changed state to administratively down
Nov 19 20:43:11.407: %LINK-5-CHANGED: Interface FastEthernet0/1, changed state to administratively down
Nov 19 20:43:11.427: %LINK-5-CHANGED: Interface Ethernet1/0, changed state to administratively down
Nov 19 20:43:11.435: %LINK-5-CHANGED: Interface Ethernet1/1, changed state to a administratively down
Nov 19 20:43:11.447: %LINK-5-CHANGED: Interface Ethernet1/2, changed state to a administratively down
Nov 19 20:43:11.451: %LINK-5-CHANGED: Interface Ethernet1/3, changed state to a administratively down
Nov 19 20:43:11.451: %LINK-5-CHANGED: Interface Ethernet2/0, changed state to a administratively down
Nov 19 20:43:11.455: %LINK-5-CHANGED: Interface Ethernet2/1, changed state to a administratively down
Nov 19 20:43:11.455: %LINK-5-CHANGED: Interface Ethernet2/2, changed state to a administratively down
Nov 19 20:43:11.455: %LINK-5-CHANGED: Interface Ethernet2/3, changed state to a administratively down
R2#
R2#
R2#
R2#
R2#
R2#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#hostname R2
R2(config)#no ip domain-lookup
R2(config)banner motd # R2, ENCOR Skills Assessment#
R2(config)line con 0
R2(config-line)echo -e "Press any key to continue...timeout 0"
R2(config-line)# logging synchronous
R2(config-line)# exit
R2(config)interface el0
R2(config-if)# ip address 209.165.200.226 255.255.255.224
R2(config-if)# ip address fe80::2:1 link-local
R2(config-if)# love address 2001:db8:200::1/64
R2(config-if)# no shutdown
R2(config-if)# exit
R2(config)interface loopback 0
R2(config-if)# ip address 2.2.2.2 255.255.255.255
R2(config-if)# love address fe80::2:3 link-local
R2(config-if)# love address 2001:db8:2222::1/128
R2(config-if)# no shutdown
R2(config-if)# exit
R2(config)# exit
*Nov 19 20:47:15.983: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up
R2(config-if)# exit
*Nov 19 20:47:15.983: %LINK-3-UPDOWN: Interface Ethernet0/0, changed state to up
*Nov 19 20:47:16.983: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to up
R2(config-if)# exit
R2(config)#
R2(config)#

```

solarwinds | Solar-PuTTY *free tool*

© 2019 SolarWinds Worldwide

8:47 p. m.
19/11/2022

Figura 3. Configuración Router R2

Router R3

```

hostname R3
ipv6 unicast-routing
no ip domain lookup

```

```
banner motd # R3, ENCOR Skills Assessment#
line con 0
exec-timeout 0 0
logging synchronous
exit
interface e1/0
ip address 10.27.11.1 255.255.255.0
ipv6 address fe80::3:2 link-local
ipv6 address 2001:db8:100:1011::1/64
no shutdown
exit
interface e1/1
ip address 10.27.13.3 255.255.255.0
ipv6 address fe80::3:3 link-local
ipv6 address 2001:db8:100:1010::2/64
no shutdown
exit
```

exit

```

3, changed state to down
*Nov 19 20:43:13.267: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/
3, changed state to down
*Nov 19 20:43:13.271: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/
*Nov 19 20:43:13.271: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/
1, changed state to down
*Nov 19 20:43:13.271: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/
2, changed state to down
*Nov 19 20:43:13.271: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/
3, changed state to down
*Nov 19 20:43:14.439: %LINK-5-CHANGED: Interface FastEthernet0/0, changed state
to administratively down
*Nov 19 20:43:14.439: %LINK-5-CHANGED: Interface FastEthernet0/1, changed state
to administratively down
*Nov 19 20:43:14.443: %LINK-5-CHANGED: Interface Ethernet1/0, changed state to a
administratively down
*Nov 19 20:43:14.471: %LINK-5-CHANGED: Interface Ethernet1/1, changed state to a
administratively down
*Nov 19 20:43:14.479: %LINK-5-CHANGED: Interface Ethernet1/2, changed state to a
administratively down
*Nov 19 20:43:14.487: %LINK-5-CHANGED: Interface Ethernet1/3, changed state to a
administratively down
*Nov 19 20:43:14.491: %LINK-5-CHANGED: Interface Ethernet2/0, changed state to a
administratively down
*Nov 19 20:43:14.491: %LINK-5-CHANGED: Interface Ethernet2/1, changed state to a
administratively down
*Nov 19 20:43:14.491: %LINK-5-CHANGED: Interface Ethernet2/2, changed state to a
administratively down
*Nov 19 20:43:14.491: %LINK-5-CHANGED: Interface Ethernet2/3, changed state to a
administratively down
R3#
R3#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#hostname R3
R3(config)#ip unicast-routing
R3(config)#no ip domain lookup
R3(config)#banner motd # R3, ENCOR Skills Assessment#
R3(config)#line con 0
R3(config-line)# exec-timeout 0 0
R3(config-line)# logging synchronous
R3(config-line)# exit
R3(config)#interface e1/0
R3(config-if)# ip address 10.27.11.1 255.255.255.0
R3(config-if)# ipv6 address fe80::1:2 link-local
R3(config-if)# ipv6 address 2001:db8:100:1011::1/64
R3(config-if)# no shutdown
R3(config-if)# exit
R3(config)#interface e1/1
R3(config-if)# ip address 10.27.13.3 255.255.255.0
R3(config-if)# ipv6 address 2001:db8:100:1010::2/64
R3(config-if)# no shutdown
R3(config-if)# exit
R3(config)#
*Nov 19 20:48:26.003: %LINK-3-UPDOWN: Interface Ethernet1/0, changed state to up
*Nov 19 20:48:27.015: %LINK-3-UPDOWN: Interface Ethernet1/1, changed state to up
R3(config)#
*Nov 19 20:48:27.003: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/0, changed state to up
*Nov 19 20:48:28.015: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/1, changed state to up
R3(config)#
R3(config)#

```

solarwinds | Solar-PuTTY *free tool* © 2019 SolarWinds Worldwide

13°C ESP 8:48 p. m. 19/11/2022

Figura 4. Configuración Router R3

Switch D1

```

hostname D1
ip routing
ipv6 unicast-routing
no ip domain lookup
banner motd # D1, ENCOR Skills Assessment#
line con 0
exec-timeout 0 0
logging synchronous
exit
vlan 100
name Management
exit
vlan 101
name UserGroupA

```

```
exit
vlan 102
  name UserGroupB
  exit
vlan 999
  name NATIVE
  exit
interface e1/2
  no switchport
  ip address 10.27.10.2 255.255.255.0
  ipv6 address fe80::d1:1 link-local
  ipv6 address 2001:db8:100:1010::2/64
  no shutdown
  exit
interface vlan 100
  ip address 10.27.100.1 255.255.255.0
  ipv6 address fe80::d1:2 link-local
  ipv6 address 2001:db8:100:100::1/64
  no shutdown
  exit
interface vlan 101
  ip address 10.27.101.1 255.255.255.0
  ipv6 address fe80::d1:3 link-local
  ipv6 address 2001:db8:100:101::1/64
  no shutdown
  exit
interface vlan 102
  ip address 10.27.102.1 255.255.255.0
  ipv6 address fe80::d1:4 link-local
  ipv6 address 2001:db8:100:102::1/64
  no shutdown
  exit
  ip dhcp excluded-address 10.27.101.1 10.27.101.109
  ip dhcp excluded-address 10.27.101.141 10.27.101.254
  ip dhcp excluded-address 10.27.102.1 10.27.102.109
  ip dhcp excluded-address 10.27.102.141 10.27.102.254
  ip dhcp pool VLAN-101
    network 10.27.101.0 255.255.255.0
    default-router 10.27.101.254
    exit
  ip dhcp pool VLAN-102
    network 10.27.102.0 255.255.255.0
    default-router 10.27.102.254
```

```

exit
interface range e0/0-3,e1/0-1,e1/3,e2/0-3,e3/0-3
shutdown
exit

```

```

D1(config)# 
D1(config)# interface e1/2
D1(config-if)# no switchport
D1(config-if)# ip address 10.27.10.2 255.255.255.0
D1(config-if)# ipv6 address fe80::db8:100%101::2/64
D1(config-if)# no shutdown
D1(config-if)# exit
D1(config)# interface vlan 100
D1(config-if)# ip address 10.27.100.1 255.255.255.0
D1(config-if)# ipv6 address fe80::db8:100%101::1/64
D1(config-if)# no shutdown
D1(config-if)# exit
D1(config)# interface vlan 101
D1(config-if)# ip address 10.27.101.1 255.255.255.0
D1(config-if)# ipv6 address fe80::db8:100%101::1/64
D1(config-if)# no shutdown
D1(config-if)# exit
D1(config)# interface vlan 102
D1(config-if)# ip address 10.27.102.1 255.255.255.0
D1(config-if)# ipv6 address fe80::db8:102%102::1/64
D1(config-if)# no shutdown
D1(config-if)# exit
D1(config)# ip dhcp excluded-address 10.27.101.1 10.27.101.100
D1(config)# ip dhcp excluded-address 10.27.101.141 10.27.101.254
D1(config)# ip dhcp excluded-address 10.27.102.1 10.27.102.109
D1(config)# ip dhcp excluded-address 10.27.102.141 10.27.102.254
D1(config)# ip dhcp pool VLAN-101
D1(config-dhcp)# network 10.27.101.0 255.255.255.0
D1(config-dhcp)# default-router 10.27.101.254
D1(config-dhcp)# exit
D1(config)# ip dhcp pool VLAN-102
D1(config-dhcp)# network 10.27.102.0 255.255.255.0
D1(config-dhcp)# default-router 10.27.102.254
D1(config)# exit
D1(config)# interface range e0/0-3,e1/0-1,e1/3,e2/0-3,e3/0-3
D1(config-if-range)# shutdown
D1(config-if-range)# exit
D1(config)# 
Nov 20 01:51:31.148: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
D1(config)#

```

© 2019 SolarWinds Worldwide, Inc.

Solarwinds | Solar-PuTTY *free tool* | 8:51 p. m. | 19/11/2022

Figura 5. Configuración Switch D1

Switch D2

```

hostname D2
ip routing
ipv6 unicast-routing
no ip domain lookup
banner motd # D2, ENCOR Skills Assessment#
line con 0

```

```
exec-timeout 0 0
logging synchronous
exit
vlan 100
name Management
exit
vlan 101
name UserGroupA
exit
vlan 102
name UserGroupB
exit
vlan 999
name NATIVE
exit
interface e1/0
no switchport
ip address 10.27.11.2 255.255.255.0
ipv6 address fe80::d1:1 link-local
ipv6 address 2001:db8:100:1011::2/64
no shutdown
exit
interface vlan 100
ip address 10.27.100.2 255.255.255.0
ipv6 address fe80::d2:2 link-local
ipv6 address 2001:db8:100:100::2/64
no shutdown
exit
interface vlan 101
ip address 10.27.101.2 255.255.255.0
ipv6 address fe80::d2:3 link-local
ipv6 address 2001:db8:100:101::2/64
no shutdown
exit
interface vlan 102
ip address 10.27.102.2 255.255.255.0
ipv6 address fe80::d2:4 link-local
ipv6 address 2001:db8:100:102::2/64
no shutdown
exit
ip dhcp excluded-address 10.27.101.1 10.27.101.209
ip dhcp excluded-address 10.27.101.241 10.27.101.254
ip dhcp excluded-address 10.27.102.1 10.27.102.209
```

```

ip dhcp excluded-address 10.27.102.241 10.27.102.254
ip dhcp pool VLAN-101
  network 10.27.101.0 255.255.255.0
  default-router 27.0.101.254
  exit
ip dhcp pool VLAN-102
  network 10.27.102.0 255.255.255.0
  default-router 10.27.102.254
  exit
interface range e0/0-3,e1/1-3,e2/0-3,e3/0-3
  shutdown
exit

```




Figura 6. Configuración Switch D1

Switch A1

```
hostname A1
no ip domain lookup
banner motd # A1, ENCOR Skills Assessment#
line con 0
exec-timeout 0 0
logging synchronous
exit
vlan 100
name Management
exit
vlan 101
name UserGroupA
exit
vlan 102
name UserGroupB
exit
vlan 999
name NATIVE
exit
interface vlan 100
ip address 10.27.100.3 255.255.255.0
ipv6 address fe80::a1:1 link-local
ipv6 address 2001:db8:100:100::3/64
no shutdown
exit
interface range e0/0,e0/3,e1/0,e2/1-3,e3/0-3
shutdown
exit
```

```


Nov 20 01:42:29.295: %LINKDOWN: Line protocol on Interface ethernet3/2, changed state to up
Nov 20 01:42:29.295: %LINKDOWN: Line protocol on Interface ethernet3/3, changed state to up
...
...
...
All(config-terminal)
Enter configuration commands, one per line. End with CNTL/Z.
[config]
[config]#banner motd # A1, INCON Skills Assessment#
[config]#exec-timeout 0 0
[config]#logging synchronous
[config]#telnet 192.168.1.12
[config]#vlan 100
[config]#name Management
[config]#vlandb exit
[config]#vlan 181
[config]#name UserDroupA
[config]#vlandb exit
[config]#vlandb name UserDroupB
[config]#vlandb exit
[config]#vlandb name NATIVE
[config]#vlandb exit
[config]#vlandb name plan 100
[config]#ip address 10.27.100.3 255.255.255.0
[config]#ip default-gateway 10.27.100.1
[config]#ip link address 00:0c:8d:10:00:03
[config]#no shutdown
[config]#exit
[config]#interface range eth0/0,eth3/1,eth4/0,eth2/1-,eth3/0-3
[config]#ip address 10.27.100.3 255.255.255.0
[config]#ip link address 00:0c:8d:10:00:03
[config]#exit
All(config)#
...
...
...
Nov 20 01:42:40.128: %LINKDOWN: Line protocol on Interface vlan100, changed state to down
Nov 20 01:42:40.128: %LINKDOWN: Interface Vlan100, changed state to administratively down
...
...
...
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
Nov 20 01:42:40.142: %LINKDOWN: Line 5-COMPRESSED Interface Ethernet4/0, changed state to administratively down
All(config)#
...
...
...
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/0, changed state to down
All(config)#
...
...
...
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
Nov 20 01:42:40.148: %LINKDOWN: Line protocol on Interface ethernet4/1, changed state to down
All(config)#
...
...
...

```

Figura 7. Configuración Switch A1

- Save the running configuration to startup-config on all devices.
- Configure PC 1 and PC 4 host addressing as shown in the addressing table. Assign a default gateway address of 10.27.100.254 which will be the HSRP virtual IP address used in Part 4.

PC 1:



```
Welcome to Virtual PC Simulator, version 8.8.2
Authorised to be public
Build time: Aug 27 2021 11:23:00
Copyright (c) 2000-2021, Paul Ning (mironix@gmail.com)
All rights reserved.

vics is free software, distributed under the terms of the "BSD" licence.
More information about the licence can be found at www.vics.org.
For more information, please visit www.freecode.com.cn.

Press '?' to get help.

Bootstrapping the startup file.

vics> help
for commands, "vics&help", use ? for help.
for command, "vics&enable", use ! for help.
for command, "vics&enable", ! for help.


vics help
'      Print help
arp      Clear arp cache, show arp, show arp history
arp[arp]      Clear IPv4/ICMPv4 arp neighbor cache, command history
arpneighbor[arpneighbor]      Show arp neighbor table via ICMP
distance[distance]      Set the target position (choose mode)
mac[mac]      Show MAC address of selected device, set ROM
ping[ping ...]      Print help
ping[ping ...]      Ping HOST with ICMP (default) or TCP/UDP, see ping ?
relay[relay ...]      Configure the current VNC1 IP settings, see ip ?
show[show ...]      Show the configuration of selected device, see show ?
trace[trace ...]      Trace packet relay between VNC ports, see relay ?
vics[vics ...]      Save the configuration to the file FILENAME
vics[<file>]      Print the information of VNCs (default), see show ?
trace[trace ...]      Print the path packets take to network
trace[trace ...]      Print the path packets take to network
trace[trace ...]      Print the path packets take to network

To get command syntax help, please enter 'T' as an argument of the command.

vics> ip 10.27.100.6 255.255.255.0
Checking for duplicate address...
vics> ip 10.27.100.6 255.255.255.0
vics>
```

Figura 8. Configuración PC1

PC 4:



```
Welcome to Virtual PC Simulator, version 8.8.2
Authorised to be public
Build time: Aug 27 2021 11:23:00
Copyright (c) 2000-2021, Paul Ning (mironix@gmail.com)
All rights reserved.

vics is free software, distributed under the terms of the "BSD" licence.
More information about the licence can be found at www.vics.org.
For more information, please visit www.freecode.com.cn.

Press '?' to get help.

Bootstrapping the startup file.

vics> help
for commands, "vics&help", use ? for help.
for command, "vics&enable", use ! for help.
for command, "vics&enable", ! for help.

vics help
'      Print help
arp      Clear arp cache, show arp, show arp history
arp[arp]      Clear IPv4/ICMPv4 arp neighbor cache, command history
arpneighbor[arpneighbor]      Show arp neighbor table via ICMP
distance[distance]      Set the target position (choose mode)
mac[mac]      Show MAC address of selected device, set ROM
ping[ping ...]      Print help
ping[ping ...]      Ping HOST with ICMP (default) or TCP/UDP, see ping ?
relay[relay ...]      Configure the current VNC1 IP settings, see ip ?
show[show ...]      Show the configuration of selected device, see show ?
trace[trace ...]      Trace packet relay between VNC ports, see relay ?
vics[vics ...]      Save the configuration to the file FILENAME
vics[<file>]      Print the information of VNCs (default), see show ?
trace[trace ...]      Print the path packets take to network
trace[trace ...]      Print the path packets take to network
trace[trace ...]      Print the path packets take to network

To get command syntax help, please enter 'T' as an argument of the command.

vics> ip 10.27.100.6 255.255.255.0
Checking for duplicate address...
vics> ip 10.27.100.6 255.255.255.0
vics>
```

Figura 9. Configuración PC2

Configure the Layer 2 Network and Host Support

In this part of the Skills Assessment, you will complete the Layer 2 network configuration and set up basic host support. At the end of this part, all the switches should be able to communicate. PC2 and PC3 should receive addressing from DHCP and SLAAC.

Your configuration tasks are as follows:

Task#	Task	Specification	Points
2.1	On all switches, configure IEEE 802.1Q trunk interfaces on interconnecting switch links	Enable 802.1Q trunk links between: <ul style="list-style-type: none">• D1 and D2• D1 and A1• D2 and A1	6
2.2	On all switches, change the native VLAN on trunk links.	Use VLAN 999 as the native VLAN.	6
2.3	On all switches, enable the Rapid Spanning-Tree Protocol.	Use Rapid Spanning Tree.	3
2.4	On D1 and D2, configure the appropriate RSTP root bridges based on the information in the topology diagram. D1 and D2 must provide backup in case of root bridge failure.	Configure D1 and D2 as root for the appropriate VLANs with mutually supporting priorities in case of switch failure.	2
2.5	On all switches, create LACP EtherChannels as shown in the topology diagram.	Use the following channel numbers: <ul style="list-style-type: none">• D1 to D2 – Port channel 12• D1 to A1 – Port channel 1• D2 to A1 – Port channel 2	3
2.6	On all switches, configure host access ports connecting to PC1, PC2, PC3, and PC4.	Configure access ports with appropriate VLAN settings as shown in the topology diagram. Host ports should transition immediately to forwarding state.	4
2.7	Verify IPv4 DHCP services.	PC2 and PC3 are DHCP clients and should be receiving valid IPv4 addresses.	1

Task#	Task	Specification	Points
2.8	Verify local LAN connectivity.	<p>PC1 should successfully ping:</p> <ul style="list-style-type: none"> • D1: 10.27.100.1 • D2: 10.27.100.2 • PC4: 10.27.100.6 <p>PC2 should successfully ping:</p> <ul style="list-style-type: none"> • D1: 10.27.102.1 • D2: 10.27.102.2 <p>PC3 should successfully ping:</p> <ul style="list-style-type: none"> • D1: 10.27.101.1 • D2: 10.27.101.2 <p>PC4 should successfully ping:</p> <ul style="list-style-type: none"> • D1: 10.27.100.1 • D2: 10.27.100.2 • PC1: 10.27.100.5 	1

Tabla 2. Configuración de la red de capa 2 y la compatibilidad con el host

Task 2.1 – 2.6


Switch D1:

```

interface range e2/0-3
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk native vlan 999
channel-group 12 mode active
no shutdown
exit
interface range e0/1-2
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk native vlan 999
channel-group 1 mode active
no shutdown
exit
spanning-tree mode rapid-pvst
spanning-tree vlan 100,102 root primary
spanning-tree vlan 101 root secondary
interface e0/0
switchport mode access
switchport access vlan 100
spanning-tree portfast

```

no shutdown
 exit
 end



```

D1(config)#  

D1(config)#  

*Nov 28 03:42:51.029: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).  

D1(config)#  

D1(config)#  

D1(config)#  

D1(config)#  

D1(config)#
D1(config)#interface range e2/0-3
D1(config-if-range)#switchport mode trunk
D1(config-if-range)#switchport trunk encapsulation dot1q
D1(config-if-range)#switchport native vlan 999
D1(config-if-range)#channel-group 12 mode active
Creating a port-channel interface Port-channel 12
D1(config-if-range)#no shutdown
D1(config-if-range)#exit
D1(config)#interface range e0/1-2
D1(config-if-range)#switchport mode trunk
D1(config-if-range)#switchport trunk encapsulation dot1q
D1(config-if-range)#switchport mode trunk
D1(config-if-range)#switchport native vlan 999
D1(config-if-range)#channel-group 1 mode active
Creating a port-channel interface Port-channel 1
D1(config-if-range)#no shutdown
D1(config-if-range)#exit
D1(config)#spanning-tree mode rapid-pvst
D1(config)#spanning-tree root primary
D1(config)#spanning-tree vlan 101 not secondary
D1(config)#interface e0/0
D1(config-if)#switchport mode access
D1(config-if)#switchport access vlan 100
% Access VLAN does not exist. Creating VLAN 100
D1(config)#spanning-tree portfast
D1(config)#spanning-tree portfast enable
% portfast is enabled on ports connected to a single host. Connecting hubs, concentrators, switches, bridges, etc... to this interface when portFast is enabled, can cause temporary bridging loops. Use with CAUTION
D1#
*Nov 28 03:42:58.257: %SYS-5-CONFIG_I: Configured from console by console
D1#
*Nov 28 03:42:58.697: %LINK-3-UPDOWN: Interface Ethernet2/0, changed state to up
*Nov 28 03:42:58.698: %LINK-3-UPDOWN: Interface Ethernet2/0, changed state to up
*Nov 28 03:42:58.698: %LINK-3-UPDOWN: Interface Ethernet2/2, changed state to up
*Nov 28 03:42:58.698: %LINK-3-UPDOWN: Interface Ethernet2/2, changed state to up
*Nov 28 03:42:58.698: %LINK-3-UPDOWN: Interface Ethernet2/3, changed state to up
*Nov 28 03:42:58.698: %LINK-3-UPDOWN: Interface Ethernet2/3, changed state to up
*Nov 28 03:42:58.698: %LINK-3-UPDOWN: Interface Ethernet2/1, changed state to up
*Nov 28 03:42:58.698: %LINK-3-UPDOWN: Interface Ethernet2/1, changed state to up
*Nov 28 03:42:58.702: %LINK-3-UPDOWN: Interface ethernet0/0, changed state to up
*Nov 28 03:42:58.702: %LINK-3-UPDOWN: Interface Vlan100, changed state to up
*Nov 28 03:42:58.702: %LINKPROT-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to up
*Nov 28 03:42:59.022: %LINKPROT-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to up
*Nov 28 03:42:59.702: %LINKPROT-5-UPDOWN: Line protocol on Interface Vlan100, changed state to up
D1#
*Nov 28 03:43:08.647: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/1 (999), with A1 Ethernet0/1 (1).
D1#
*Nov 28 03:43:07.496: %EIG-5-L3DYNAMICBOL2: #2<0 suspended: LACP currently not enabled on the remote port.
*Nov 28 03:43:07.542: %EIG-5-L3DYNAMICBOL2: #0<1 suspended: LACP currently not enabled on the remote port.
*Nov 28 03:43:07.599: %EIG-5-L3DYNAMICBOL2: #2<3 suspended: LACP currently not enabled on the remote port.
*Nov 28 03:43:07.656: %EIG-5-L3DYNAMICBOL2: #0<2 suspended: LACP currently not enabled on the remote port.
*Nov 28 03:43:07.696: %EIG-5-L3DYNAMICBOL2: #2<1 suspended: LACP currently not enabled on the remote port.
*Nov 28 03:43:08.033: %EIG-5-L3DYNAMICBOL2: #2<1 suspended: LACP currently not enabled on the remote port.
D1#
*Nov 28 03:43:19.630: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/2 (999), with A1 Ethernet0/2 (1).
D1#
D1#
*Nov 28 03:43:49.397: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/1 (999), with A1 Ethernet0/1 (1).
*Nov 28 03:43:50.559: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
D1#
*Nov 28 03:44:14.581: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/2 (999), with A1 Ethernet0/2 (1).
D1#
*Nov 28 03:44:46.513: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/1 (999), with A1 Ethernet0/1 (1).
D1#
*Nov 28 03:44:47.717: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
D1#
*Nov 28 03:45:05.628: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/2 (999), with A1 Ethernet0/2 (1).
D1#
*Nov 28 03:45:39.031: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/1 (999), with A1 Ethernet0/1 (1).
D1#
*Nov 28 03:45:44.879: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
D1#
*Nov 28 03:46:03.803: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/2 (999), with A1 Ethernet0/2 (1).
D1#
D1#
*Nov 28 03:46:38.096: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
*Nov 28 03:46:38.096: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/1 (999), with A1 Ethernet0/1 (1).
D1#
*Nov 28 03:46:55.748: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/2 (999), with A1 Ethernet0/2 (1).
D1#
D1#
D1#

```

Figura 10. Configuración Switch D1 Tarea 2.1 – 2.6

```

R1
R2
R3
D1 ✘
D2
A1
PC

# show interfaces trunk
Port Mode Encapsulation Status Native VLAN
port 1 on 802.1q trunking 999
port 2 on 802.1q trunking 999

Port Vlans allowed on trunk
port 1 1-4094
port 2 1-4094

Port Vlans allowed and active in management domain
port 1 1,100
port 2 1,100

Port Vlans in spanning tree forwarding state and not pruned
port 1 1,100
port 2 1,100

Nov 28 03:51:58.304: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not Full duplex), with R1 Ethernet1/2 (full duplex).
# show run | include spanning-tree
spanning-tree mode rapid-pvst
spanning-tree priority 1024
spanning-tree vlan 100,102 priority 24576
spanning-tree vlan 101 priority 28672
spanning-tree portfast edge
spanning-tree portfast
Nov 28 03:51:47.292: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
# show run int
# Nov 28 03:51:30.494: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
# show run config
building configuration...
current configuration : 110 bytes
interface Ethernet0/0
switchport access vlan 100
switchport mode access
spanning-tree portfast edge
spanning-tree portfast
Nov 28 03:54:20.569: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not Full duplex), with R1 Ethernet1/2 (full duplex).
# 

```

Figura 11. Verificación Configuración Switch D1 Tarea 2.1 – 2.6

Switch D2:

```

interface range e2/0-3
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk native vlan 999
channel-group 12 mode active
no shutdown
exit
interface range e0/1-2
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk native vlan 999
channel-group 1 mode active
no shutdown

```

```

exit
spanning-tree mode rapid-pvst
spanning-tree vlan 100 root primary
spanning-tree vlan 100,102 root secondary
interface e0/0
switchport mode access
switchport access vlan 102
spanning-tree portfast
no shutdown
exit
end

```

```

R1 R2 R3 D1 D2 A1 PC
[...]
22(config)#interface range e2/0-3
22(config-if-range)#switchport trunk encapsulation dot1q
22(config-if-range)#switchport mode trunk
22(config-if-range)#switchport trunk native vlan 999
22(config-if-range)#channel-group 12 mode active
Creating a port-channel interface Port-channel 12
22(config-if-range)#shutdown
22(config-if-range)#exit
22(config)#interface range e0/1-2
22(config-if-range)#switchport trunk encapsulation dot1q
22(config-if-range)#switchport mode trunk
22(config-if-range)#switchport trunk native vlan 999
22(config-if-range)#channel-group 1 mode active
Creating a port-channel interface Port-channel 1
22(config-if-range)#shutdown
22(config-if-range)#exit
22(config)#spanning-tree mode rapid-pvst
22(config)#spanning-tree vlan 100 root primary
22(config)#spanning-tree vlan 100,102 root secondary
22(config)#spanning-tree mode portfast
22(config-if-range)#switchport mode access
22(config-if-range)#switchport access vlan 102
22(config-if-range)#spanning-tree portfast
Warning: portfast mode can only be enabled on ports connected to a single
host. Connecting hubs, concentrators, switches, bridges, etc., to this
interface when portfast is enabled, can cause temporary bridging loops.
Use with CAUTION
#Portfast has been configured on Ethernet8/0 but will only
#have effect when the interface is in a non-trunking mode.
22(config-if)#shutdown
22(config-if)#exit
22(config)#end
22#
22#Nov 29 03:48:01.537: %SYS-5-CONFIG_I: Configured from console by console
22#Nov 29 03:48:01.537: %LINK-3-UPDOWN: Interface Ethernet2/0, changed state to up
22#Nov 29 03:48:01.537: %LINK-3-UPDOWN: Interface Ethernet2/1, changed state to up
22#Nov 29 03:48:01.537: %LINK-3-UPDOWN: Interface Ethernet2/2, changed state to up
22#Nov 29 03:48:01.537: %LINK-3-UPDOWN: Interface Ethernet2/3, changed state to up
22#Nov 29 03:48:01.537: %LINK-3-UPDOWN: Interface Ethernet8/1, changed state to up
22#Nov 29 03:48:01.537: %LINK-3-UPDOWN: Interface Ethernet8/0, changed state to up
22#Nov 29 03:48:01.537: %LINK-3-UPDOWN: Interface Ethernet1/0, changed state to up
22#Nov 29 03:48:02.545: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/0, changed state to up
22#Nov 29 03:48:02.545: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/1, changed state to up
22#Nov 29 03:48:02.545: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/2, changed state to up
22#Nov 29 03:48:02.545: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet2/3, changed state to up
22#
22#Nov 29 03:48:02.559: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet8/0, changed state to up
22#Nov 29 03:48:02.559: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan102, changed state to up
22#
22#Nov 29 03:48:02.559: %LINK-3-UPDOWN: Interface Vlan102, changed state to up
22#
22#Nov 29 03:48:11.369: %EC-5-L300NTBNDL2: Eth0/1 suspended: LACP currently not enabled on the remote port.
22#Nov 29 03:48:11.458: %EC-5-L300NTBNDL2: Eth0/2 suspended: LACP currently not enabled on the remote port.
22#Nov 29 03:48:12.067: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan100, changed state to up
22#
22#Nov 29 03:48:36.529: %LINK-3-UPDOWN: Interface Vlan101, changed state to up
22#Nov 29 03:48:37.334: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan101, changed state to up
22#
22#

```

10:48 p. m.
19/11/2022

Figura 12. Configuración Switch D2 Tarea 2.1 – 2.6



Figura 13. Verificación Configuración Switch D2 Tarea 2.1 – 2.6

Switch A1:

```
spanning-tree mode rapid-pvst
interface range e0/1-2
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk native vlan 999
channel-group 1 mode active
no shutdown
exit
interface range e1/1-2
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk native vlan 999
channel-group 2 mode active
```

```
no shutdown
exit
interface e1/3
switchport mode access
switchport access vlan 101
spanning-tree portfast
no shutdown
exit
interface e2/0
switchport mode access
switchport access vlan 100
spanning-tree portfast
no shutdown
exit
end
```

```

A1(config)# spanning-tree mode rapid-pvst
A1(config-if-range)#switchport trunk encapsulation dot1q
A1(config-if-range)#switchport mode trunk
A1(config-if-range)#switchport trunk native vlan 999
A1(config-if-range)#channel-group 1 mode active
Creating a port-channel interface Port-channel 1
A1(config-if-range)#no shutdown
A1(config-if-range)#exit
A1(config-if-range)#interface e1/2
A1(config-if-range)#switchport mode access
A1(config-if-range)#switchport access vlan 101
A1(config-if-range)#spanning-tree portfast
Warning: portfast should only be enabled on ports connected to a single
host. Connecting hubs, concentrators, switches, bridges, etc... to this
interface when portfast is enabled, can cause temporary bridging loops.
Use with CAUTION
No portfast has been configured on Ethernet1/3 but will only
have effect when the interface is in a non-trunking mode.
A1(config-if-range)#no shutdown
A1(config-if-range)#exit
A1(config-if-range)#interface e2/0
A1(config-if-range)#switchport mode access
A1(config-if-range)#switchport access vlan 100
A1(config-if-range)#spanning-tree portfast
Warning: portfast should only be enabled on ports connected to a single
host. Connecting hubs, concentrators, switches, bridges, etc... to this
interface when portfast is enabled, can cause temporary bridging loops.
Use with CAUTION
No portfast has been configured on Ethernet2/0 but will only
have effect when the interface is in a non-trunking mode.
A1(config-if-range)#no shutdown
A1(config-if-range)#exit
A1(config-if-range)#exit
A1#
Nov 20 03:48:24.854: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/2 (1), with D1 Ethernet0/2 (999).
A1#
Nov 20 03:48:26.558: %SYS-5-CONFIG_I: Configured from console by console
Nov 20 03:48:26.813: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/1, changed state to down
Nov 20 03:48:26.813: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/2, changed state to down
A1#
Nov 20 03:48:32.477: %LINEPROTO-5-UPDOWN: Line protocol on Interface Port-channel, changed state to up
A1#
Nov 20 03:48:36.956: %EC-5-L3DONTBNDL2: E1/2 suspended: LACP currently not enabled on the remote port.
Nov 20 03:48:37.414: %EC-5-L3DONTBNDL2: E1/1 suspended: LACP currently not enabled on the remote port.
A1#
A1#
A1#

```

Icons at the bottom include a circular arrow, a blue square, a yellow sun, a temperature icon (13°C), a signal strength icon, and an ESP icon. The status bar shows the time (10:49 p. m.), date (19/11/2022), and a notification icon with the number 7.

Figura 14. Configuración Switch A1 Tarea 2.1 – 2.6




```
cli(config-if)#switchport mode access
cli(config-if)#switchport access vlan 100
cli(config-if)#spanning-tree portfast
!Portfast should only be enabled on ports connected to a single host. Connecting hubs, concentrators, switches, bridges, etc... to this interface when portfast is enabled, can cause temporary bridging loops.
Use with CAUTION
!Portfast has been configured on Ethernet2/0 but will only have effect when the interface is in a non-trunking mode.
cli(config-if)#no shutdown
cli(config-if)#
cli(config)#end
!# Nov 28 03:48:24.854: %CDP-4-NATIVE_VLAN_MISMATCH: Native VLAN mismatch discovered on Ethernet0/2 (1), with D1 Ethernet0/2 (999).
!##
Nov 28 03:48:26.558: %SYS-5-CONFIG_I: Configured from console by console
Nov 28 03:48:26.813: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/1, changed state to down
Nov 28 03:48:26.813: %LINEPROTO-5-UPDOWN: Line protocol on Interface ethernet1/2, changed state to down
!##
Nov 28 03:48:32.477: %LINEPROTO-5-UPDOWN: Line protocol on Interface Port-channel1, changed state to up
!##
Nov 28 03:48:36.956: %SC-5-L3000TBNDL2: Eth1/2 suspended: LACP currently not enabled on the remote port.
Nov 28 03:48:37.454: %SC-5-L3000TBNDL2: Eth1/3 suspended: LACP currently not enabled on the remote port.
!##
!#show int trunk
Current configuration : 110 bytes
interface Ethernet1/2
 switchport access vlan 100
 switchport mode access
 spanning-tree portfast edge
 end
!#show run int e2/0
Building configuration...
Current configuration : 110 bytes
interface Ethernet1/2
 switchport access vlan 100
 switchport mode access
 spanning-tree portfast edge
 end
!#
```



Figura 15. Verificación Configuración Switch D2 Tarea 2.1 – 2.6

TASK 2.8 Verifique la conectividad LAN local.

PC 1:



```
PC1: ping 10.27.198.1
64 bytes from 10.27.198.1 icmp_seq=1 ttl=255 time=0.247 ms
64 bytes from 10.27.198.1 icmp_seq=2 ttl=255 time=0.244 ms
64 bytes from 10.27.198.1 icmp_seq=3 ttl=255 time=0.240 ms
64 bytes from 10.27.198.1 icmp_seq=4 ttl=255 time=0.365 ms
64 bytes from 10.27.198.1 icmp_seq=5 ttl=255 time=0.237 ms


PC1: ping 10.27.198.2
64 bytes from 10.27.198.2 icmp_seq=1 ttl=255 time=0.200 ms
64 bytes from 10.27.198.2 icmp_seq=2 ttl=255 time=0.421 ms
64 bytes from 10.27.198.2 icmp_seq=3 ttl=255 time=0.480 ms
64 bytes from 10.27.198.2 icmp_seq=4 ttl=255 time=0.444 ms
64 bytes from 10.27.198.2 icmp_seq=5 ttl=255 time=0.468 ms

PC1: ping 10.27.198.6
64 bytes from 10.27.198.6 icmp_seq=1 ttl=64 time=0.277 ms
64 bytes from 10.27.198.6 icmp_seq=2 ttl=64 time=0.521 ms
64 bytes from 10.27.198.6 icmp_seq=3 ttl=64 time=0.413 ms
64 bytes from 10.27.198.6 icmp_seq=4 ttl=64 time=0.409 ms
64 bytes from 10.27.198.6 icmp_seq=5 ttl=64 time=0.427 ms
```

Solar-PuTTY free tool | © 2019 SolarWinds Worldwide, LLC. All rights reserved. 13°C 11:02 p. m. 19/11/2022

Figura 16. Verificación conectividad LAN local PC1

PC 2:



```
Welcome to Virtual PC Simulator, version 0.8.2
Address: 127.0.0.1
Build time: Aug 23 2021 11:15:00
Copyright (c) 2007-2015, Paul Meng (mirmshi@gmail.com)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sourceforge.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

PC>
PC> ping 10.27.181.1
host (10.27.181.1) not reachable

PC>
PC>
PC>
PC>
PC>
PC>
PC>
PC> ping 10.27.182.1
host (10.27.182.1) not reachable

PC>
PC> 10.27.182.2
Bad command: "10.27.182.2". Use ? for help.

PC>
PC>
PC>
PC>
PC>
PC>
PC>
PC> ping 10.27.182.1
host (10.27.182.1) not reachable

PC> ping 10.27.182.2
10.27.182.2 icmp_seq=1 timeout
10.27.182.2 icmp_seq=2 timeout
10.27.182.2 icmp_seq=3 timeout
10.27.182.2 icmp_seq=4 timeout
10.27.182.2 icmp_seq=5 timeout

PC> ping 10.27.182.1
host (10.27.182.1) not reachable

PC>
```




Figura 17. Verificación conectividad LAN local PC2

PC 3:





Figura 18. Verificación conectividad LAN local PC3

PC 4:



```
PC4$  
PC4$  
PC4$  
PC4$ ping 10.27.100.1  
64 bytes from 10.27.100.1 icmp_seq1 ttl=255 time=0.215 ms  
64 bytes from 10.27.100.1 icmp_seq2 ttl=255 time=0.479 ms  
64 bytes from 10.27.100.1 icmp_seq3 ttl=255 time=0.333 ms  
64 bytes from 10.27.100.1 icmp_seq4 ttl=255 time=0.485 ms  
64 bytes from 10.27.100.1 icmp_seq5 ttl=255 time=0.477 ms  
PC4$ ping 10.27.100.2  
64 bytes from 10.27.100.2 icmp_seq1 ttl=255 time=0.282 ms  
64 bytes from 10.27.100.2 icmp_seq2 ttl=255 time=0.482 ms  
64 bytes from 10.27.100.2 icmp_seq3 ttl=255 time=0.333 ms  
64 bytes from 10.27.100.2 icmp_seq4 ttl=255 time=0.568 ms  
64 bytes from 10.27.100.2 icmp_seq5 ttl=255 time=0.563 ms  
PC4$ ping 10.27.100.3  
64 bytes from 10.27.100.3 icmp_seq1 ttl=64 time=0.139 ms  
64 bytes from 10.27.100.3 icmp_seq2 ttl=64 time=0.157 ms  
64 bytes from 10.27.100.3 icmp_seq3 ttl=64 time=0.161 ms  
64 bytes from 10.27.100.3 icmp_seq4 ttl=64 time=0.161 ms  
64 bytes from 10.27.100.3 icmp_seq5 ttl=64 time=0.161 ms  
PC4$
```

The screenshot shows a Solar-PuTTY terminal window with several ping commands issued to hosts 10.27.100.1, 10.27.100.2, and 10.27.100.3. The pings are successful with varying round-trip times (RTTs). Below the terminal window is a Windows taskbar with icons for Start, Task View, File Explorer, Task Manager, and others. The date and time are also visible on the taskbar.

Figura 19. Verificación conectividad LAN local PC4

Escenario 2 Prueba de Habilidades Diplomado CCNP ENCOR Skills Assessment (Scenario 1)

Continuation of the Scenario 1 Configure Routing Protocols

In this part, you will configure IPv4 and IPv6 routing protocols. At the end of this part, the network should be fully converged. IPv4 and IPv6 pings to the Loopback 0 interface from D1 and D2 should be successful.

Note: Pings from the hosts will not be successful because their default gateways are pointing to the HSRP address which will be enabled in Part 4.

Your configuration tasks are as follows:

Task#	Task	Specification	Points
3.1	<p>On the “Company Network” (i.e., R1, R3, D1, and D2), configure single-area OSPFv2 in area 0.</p>	<p>Use OSPF Process ID 4 and assign the following router-IDs:</p> <ul style="list-style-type: none"> • R1: 0.0.4.1 • R3: 0.0.4.3 • D1: 0.0.4.131 • D2: 0.0.4.132 <p>On R1, R3, D1, and D2, advertise all directly connected networks / VLANs in Area 0.</p> <ul style="list-style-type: none"> • On R1, do not advertise the R1 – R2 network. • On R1, propagate a default route. Note that the default route will be provided by BGP. <p>Disable OSPFv2 advertisements on:</p> <ul style="list-style-type: none"> • D1: All interfaces except E1/2 • D2: All interfaces except E1/0 	8
3.2	<p>On the “Company Network” (i.e., R1, R3, D1, and D2), configure classic single-area OSPFv3 in area 0.</p>	<p>Use OSPF Process ID 6 and assign the following router-IDs:</p> <ul style="list-style-type: none"> • R1: 0.0.6.1 • R3: 0.0.6.3 • D1: 0.0.6.131 • D2: 0.0.6.132 <p>On R1, R3, D1, and D2, advertise all directly connected networks / VLANs in Area 0.</p> <ul style="list-style-type: none"> • On R1, do not advertise the R1 – R2 network. • On R1, propagate a default route. Note that the default route will be provided by BGP. <p>Disable OSPFv3 advertisements on:</p> <ul style="list-style-type: none"> • D1: All interfaces except E1/2 • D2: All interfaces except E1/0 	8

Task#	Task	Specification	Points
3.3	On R2 in the “ISP Network”, configure MP-BGP.	<p>Configure two default static routes via interface Loopback 0:</p> <ul style="list-style-type: none"> • An IPv4 default static route. • An IPv6 default static route. <p>Configure R2 in BGP ASN 500 and use the router-id 2.2.2.2.</p> <p>Configure and enable an IPv4 and IPv6 neighbor relationship with R1 in ASN 300.</p> <p>In IPv4 address family, advertise:</p> <ul style="list-style-type: none"> • The Loopback 0 IPv4 network (/32). • The default route (0.0.0.0/0). <p>In IPv6 address family, advertise:</p> <ul style="list-style-type: none"> • The Loopback 0 IPv4 network (/128). • The default route (::/0). 	4
3.4	On R1 in the “ISP Network”, configure MP-BGP.	<p>Configure two static summary routes to interface Null 0:</p> <ul style="list-style-type: none"> • A summary IPv4 route for 10.27.0.0/8. • A summary IPv6 route for 2001:db8:100::/48. <p>Configure R1 in BGP ASN 300 and use the router-id 1.1.1.1.</p> <p>Configure an IPv4 and IPv6 neighbor relationship with R2 in ASN 500.</p> <p>In IPv4 address family:</p> <ul style="list-style-type: none"> • Disable the IPv6 neighbor relationship. • Enable the IPv4 neighbor relationship. • Advertise the 10.27.0.0/8 network. <p>In IPv6 address family:</p> <ul style="list-style-type: none"> • Disable the Ipv4 neighbor relationship. • Enable the Ipv6 neighbor relationship. • Advertise the 2001:db8:100::/48 network. 	4

Task 3.1 – 3.4 Configurar protocolos de enrutamiento.

Router 1 (R1):

```
router ospf 4
router-id 0.0.4.1
network 10.0.10.0 0.0.0.255 area 0
network 10.0.13.0 0.0.0.255 area 0
default-information originate
exit
ipv6 router ospf 6
router-id 0.0.6.1
default-information originate
exit
interface e1/2
ipv6 ospf 6 area 0
exit
interface e1/1
ipv6 ospf 6 area 0
exit
ip route 10.27.0.0 255.0.0.0 null0
ipv6 route 2001:db8:100::/48 null0
router bgp 300
bgp router-id 1.1.1.1
neighbor 209.165.200.226 remote-as 500
neighbor 2001:db8:200::2 remote-as 500
address-family ipv4 unicast
neighbor 209.165.200.226 activate
no neighbor 2001:db8:200::2 activate
network 10.27.0.0 mask 255.0.0.0
exit-address-family
address-family ipv6 unicast
no neighbor 209.165.200.226 activate
neighbor 2001:db8:200::2 activate
network 2001:db8:100::/48
```



```

exit-address-family
address-family ipv6
no neighbor 209.165.200.225 activate
neighbor 2001:db8:200::1 activate
network 2001:db8:2222::/128
network ::/0
exit-address-family

```

```

R2#config t
R2(config)#router ospf 1
R2(config-router)#network 209.165.200.0 0.0.0.255
R2(config-router)#neighbor 209.165.200.225
R2(config-router)#exit
R2(config)#router ospf 2
R2(config-router)#network 2001:db8:200:1::0 0::ffff:ffff:ffff
R2(config-router)#neighbor 2001:db8:200:1::1
R2(config-router)#exit
R2(config)#exit
R2#exit
R2>

```

© 2019 SolarWinds Worldwide, LLC

Figura 21. Configuración protocolos de enrutamiento R2 Task 3.1 – 3.4

Router 3 (R3):

```

router ospf 4
router-id 0.0.4.3
network 10.0.11.0 0.0.0.255 area 0
network 10.0.13.0 0.0.0.255 area 0
exit
ipv6 router ospf 6
router-id 0.0.6.3

```

```

exit
interface e1/1
ipv6 ospf 6 area 0
exit
interface e1/0
ipv6 ospf 6 area 0
exit
end

```




Figura 22. Configuración protocolos de enrutamiento R3 Task 3.1 – 3.4

Switch D1:

```

router ospf 4
router-id 0.0.4.131
network 10.0.100.0 0.0.0.255 area 0
network 10.0.101.0 0.0.0.255 area 0
network 10.0.102.0 0.0.0.255 area 0

```

```
network 10.0.10.0 0.0.0.255 area 0
passive-interface default
no passive-interface e1/2
exit
ipv6 router ospf 6
router-id 0.0.6.131
passive-interface default
no passive-interface e1/2
exit
interface e1/2
ipv6 ospf 6 area 0
exit
interface vlan 100
ipv6 ospf 6 area 0
exit
interface vlan 101
ipv6 ospf 6 area 0
exit
interface vlan 102
ipv6 ospf 6 area 0
exit
end
```

```

Switch D1
Switch D1#configure terminal
Switch D1(config)#router ospf 4
Switch D1(config-router)#network 10.0.100.0 0.0.0.255 area 0
Switch D1(config-router)#network 10.0.101.0 0.0.0.255 area 0
Switch D1(config-router)#network 10.0.102.0 0.0.0.255 area 0
Switch D1(config-router)#network 10.0.11.0 0.0.0.255 area 0
Switch D1(config-router)#no passive-interface e1/2
Switch D1(config-router)#exit
Switch D1#show ip ospf 4
% IPv4 routing not enabled
Switch D1#show ip router id 0.0.0.131
% Invalid input detected at '^' marker.
Switch D1#show ip passive-interface default
% Invalid input detected at '^' marker.
Switch D1#show ip passive-interface e1/2
% Invalid input detected at '^' marker.
Switch D1#show ip interface e1/2
% Invalid input detected at '^' marker.
Switch D1#display ospf 4 area 0
%
% Invalid input detected at '^' marker.
Switch D1#exit
Switch D1#com0 is now available

Press RETURN to get started.

Nov 28 06:41:05.135: %SYS-5-CONFIG_I: Configured from console by console
Nov 28 06:41:07.030: %IFM-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
Nov 28 06:41:07.030: %IFM-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
Nov 28 06:43:32.370: %COP-4-DUPLEX_DISPATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
Nov 28 06:44:29.842: %COP-4-DUPLEX_DISPATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).

SolarWinds | Solar-PuTTY free tool | © 2019 SolarWinds Worldwide, LLC

```

Figura 23. Configuración protocolos de enrutamiento Switch D1 Task 3.1 – 3.4

Switch D2:

```

router ospf 4
router-id 0.0.4.132
network 10.0.100.0 0.0.0.255 area 0
network 10.0.101.0 0.0.0.255 area 0
network 10.0.102.0 0.0.0.255 area 0
network 10.0.11.0 0.0.0.255 area 0
passive-interface default
no passive-interface e1/0

```

```
exit
ipv6 router ospf 6
router-id 0.0.6.132
passive-interface default
no passive-interface e1/0
exit
interface e1/0
ipv6 ospf 6 area 0
exit
interface vlan 100
ipv6 ospf 6 area 0
exit
interface vlan 101
ipv6 ospf 6 area 0
exit
interface vlan 102
ipv6 ospf 6 area 0
exit
end
```

```

D2#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
D2(config)#router ospf
D2(config-router)#router-id 0.0.4.132
D2(config-router)#network 10.0.100.0 0.0.0.255 area 0
D2(config-router)#network 10.0.101.0 0.0.0.255 area 0
D2(config-router)#network 10.0.102.0 0.0.0.255 area 0
D2(config-router)#passive-interface default
D2(config-router)#no passive-interface e1/0
D2(config-router)#exit
D2(config)#interface e1/0
D2(config-if)#ospf 6 area 0
D2(config-if)#exit
D2(config)#interface vlan 100
D2(config-if)#ip ospf 6 area 0
D2(config-if)#exit
D2(config)#interface vlan 101
D2(config-if)#ip ospf 6 area 0
D2(config-if)#exit
D2(config)#interface vlan 102
D2(config-if)#ip ospf 6 area 0
D2(config-if)#exit
D2(config)#end
*Nov 20 06:47:59.510: %OSPFV3-5-ADJCHG: Process 6, Nbr 0.0.6.3 on Ethernet1/0 from FULL to DOWN, Neighbor Down: Interface down or detached
*Nov 20 06:47:59.547: %OSPFV3-5-ADJCHG: Process 6, Nbr 0.0.6.3 on Ethernet1/0 from LOADING to FULL, Loading Done
D2#
*Nov 20 06:48:00.910: %SYS-5-CONFIG_I: Configured from console by console
D2#
D2#
D2>

```

© 2019 SolarWinds Worldwide, LLC

Figura 24. Configuración protocolos de enrutamiento Switch D2 Task 3.1 – 3.4

Configure First Hop Redundancy

In this part, you will configure HSRP version 2 to provide first-hop redundancy for hosts in the “Company Network”.

Your configuration tasks are as follows:

Task#	Task	Specification	Points
4.1	On D1, create IP SLAs that test the reachability of R1 interface E1/2.	<p>Create two IP SLAs.</p> <ul style="list-style-type: none"> • Use SLA number 4 for IPv4. • Use SLA number 6 for IPv6. <p>The IP SLAs will test availability of R1 E1/2 interface every 5 seconds.</p> <p>Schedule the SLA for immediate implementation with no end time.</p> <p>Create an IP SLA object for IP SLA 4 and one for IP SLA 6.</p> <ul style="list-style-type: none"> • Use track number 4 for IP SLA 4. • Use track number 6 for IP SLA 6. <p>The tracked objects should notify D1 if the IP SLA state changes from down to up after 10 seconds, or from up to down after 15 seconds.</p>	2
4.2	On D2, create IP SLAs that test the reachability of R3 interface E1/0.	<p>Create two IP SLAs.</p> <ul style="list-style-type: none"> • Use SLA number 4 for IPv4. • Use SLA number 6 for IPv6. <p>The IP SLAs will test availability of R3 E1/0 interface every 5 seconds.</p> <p>Schedule the SLA for immediate implementation with no end time.</p> <p>Create an IP SLA object for IP SLA 4 and one for IP SLA 6.</p> <ul style="list-style-type: none"> • Use track number 4 for IP SLA 4. • Use track number 6 for IP SLA 6. <p>The tracked objects should notify D1 if the IP SLA state changes from down to up after 10 seconds, or from up to down after 15 seconds.</p>	2

Task#	Task	Specification	Points
4.3	On D1, configure HSRPv2.	<p>D1 is the primary router for VLANs 100 and 102; therefore, their priority will also be changed to 150.</p> <p>Configure HSRP version 2.</p> <p>Configure IPv4 HSRP group 104 for VLAN 100:</p> <ul style="list-style-type: none"> • Assign the virtual IP address 10.27.100.254. • Set the group priority to 150. • Enable preemption. • Track object 4 and decrement by 60. <p>Configure IPv4 HSRP group 114 for VLAN 101:</p> <ul style="list-style-type: none"> • Assign the virtual IP address 10.27.101.254. • Enable preemption. • Track object 4 to decrement by 60. <p>Configure IPv4 HSRP group 124 for VLAN 102:</p> <ul style="list-style-type: none"> • Assign the virtual IP address 10.27.102.254. • Set the group priority to 150. • Enable preemption. • Track object 4 to decrement by 60. <p>Configure IPv6 HSRP group 106 for VLAN 100:</p> <ul style="list-style-type: none"> • Assign the virtual IP address using ipv6 autoconfig. • Set the group priority to 150. • Enable preemption. • Track object 6 and decrement by 60. <p>Configure IPv6 HSRP group 116 for VLAN 101:</p> <ul style="list-style-type: none"> • Assign the virtual IP address using ipv6 autoconfig. • Enable preemption. • Track object 6 and decrement by 60. <p>Configure IPv6 HSRP group 126 for VLAN 102:</p> <ul style="list-style-type: none"> • Assign the virtual IP address using ipv6 autoconfig. • Set the group priority to 150. • Enable preemption. • Track object 6 and decrement by 60. 	8

Task#	Task	Specification	Points
	On D2, configure HSRPv2.	<p>D2 is the primary router for VLAN 101; therefore, the priority will also be changed to 150.</p> <p>Configure HSRP version 2.</p> <p>Configure IPv4 HSRP group 104 for VLAN 100:</p> <ul style="list-style-type: none"> • Assign the virtual IP address 10.27.100.254. • Enable preemption. • Track object 4 and decrement by 60. <p>Configure IPv4 HSRP group 114 for VLAN 101:</p> <ul style="list-style-type: none"> • Assign the virtual IP address 10.27.101.254. • Set the group priority to 150. • Enable preemption. • Track object 4 to decrement by 60. <p>Configure IPv4 HSRP group 124 for VLAN 102:</p> <ul style="list-style-type: none"> • Assign the virtual IP address 10.27.102.254. • Enable preemption. • Track object 4 to decrement by 60. <p>Configure IPv6 HSRP group 106 for VLAN 100:</p> <ul style="list-style-type: none"> • Assign the virtual IP address using ipv6 autoconfig. • Enable preemption. • Track object 6 and decrement by 60. <p>Configure IPv6 HSRP group 116 for VLAN 101:</p> <ul style="list-style-type: none"> • Assign the virtual IP address using ipv6 autoconfig. • Set the group priority to 150. • Enable preemption. • Track object 6 and decrement by 60. <p>Configure IPv6 HSRP group 126 for VLAN 102:</p> <ul style="list-style-type: none"> • Assign the virtual IP address using ipv6 autoconfig. • Enable preemption. • Track object 6 and decrement by 60. 	

Task 4.1 – 4.4 Configurar la redundancia del primer salto

Switch D1:

```
ip sla 4
icmp-echo 10.0.10.1
frequency 5
```

```
exit
ip sla 6
icmp-echo 2001:db8:100:1010::1
frequency 5
exit
ip sla schedule 4 life forever start-time now
ip sla schedule 6 life forever start-time now
track 4 ip sla 4
delay down 10 up 15
exit
track 6 ip sla 6
delay down 10 up 15
exit
interface vlan 100
standby version 2
standby 104 ip 10.27.100.254
standby 104 priority 150
standby 104 preempt
standby 104 track 4 decrement 60
standby 106 ipv6 autoconfig
standby 106 priority 150
standby 106 preempt
standby 106 track 6 decrement 60
exit
interface vlan 101
standby version 2
standby 114 ip 10.27.101.254
standby 114 preempt
standby 114 track 4 decrement 60
standby 116 ipv6 autoconfig
standby 116 preempt
standby 116 track 6 decrement 60
exit
interface vlan 102
standby version 2
```

```
standby 124 ip 10.27.102.254
standby 124 priority 150
standby 124 preempt
standby 124 track 4 decrement 60
standby 126 ipv6 autoconfig
standby 126 priority 150
standby 126 preempt
standby 126 track 6 decrement 60
exit
end
```

```

D1#
D1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
D1(config)#ip sla 4
D1(config-ip-sla-echo)icmp-echo 10.0.10.1
^
% Invalid input detected at '^' marker.

D1(config-ip-sla-echo)frequency 5
D1(config-ip-sla-echo)exit
D1(config)#ip sla 6
D1(config-ip-sla-echo)icmp-echo 2001:db8:100:1010::1
^
% Invalid input detected at '^' marker.

D1(config-ip-sla-echo)frequency 5
D1(config-ip-sla-echo)exit
D1(config)#ip sla schedule 4 life forever start-time now
D1(config)#ip sla schedule 6 life forever start-time now
D1(config)#track 4 delay down 10 up 15
D1(config-track)exit
D1(config-track)delay down 10 up 15
D1(config-track)exit
D1(config-track)delay down 10 up 15
D1(config-track)exit
D1(config-track)exit
D1(config-if)#standby version 2
D1(config-if)#standby 104 ip 10.27.100.254
D1(config-if)#standby 104 priority 150
D1(config-if)#standby 104 track 4 decrement 60
D1(config-if)#standby 106 ipv6 autoconfig
D1(config-if)#standby 106 priority 150
D1(config-if)#standby 106 preempt
D1(config-if)#standby 106 track 8 decrement 60
D1(config-if)exit
D1(config-if)interface vlan 100
D1(config-if)standby version 2
D1(config-if)standby 104 ip 10.27.100.254
D1(config-if)standby 104 preempt
D1(config-if)standby 104 track 4 decrement 60
D1(config-if)standby 106 ipv6 autoconfig
D1(config-if)standby 106 preempt
D1(config-if)standby 106 track 8 decrement 60
D1(config-if)exit
D1(config-if)interface vlan 102
D1(config-if)standby version 2
^
% Invalid input detected at '^' marker.

D1(config-if)#standby version 2
D1(config-if)standby 124 ip 10.27.102.254
D1(config-if)standby 124 priority 150
D1(config-if)standby 124 preempt
D1(config-if)standby 124 track 4 decrement 60
D1(config-if)standby 126 ipv6 autoconfig
D1(config-if)standby 126 preempt
D1(config-if)standby 126 track 8 decrement 60
D1(config-if)exit
D1(config-if)interface vlan 101
D1(config-if)standby version 2
D1(config-if)standby 114 ip 10.27.101.254
D1(config-if)standby 114 preempt
D1(config-if)standby 114 track 4 decrement 60
D1(config-if)standby 116 ipv6 autoconfig
D1(config-if)standby 116 preempt
D1(config-if)standby 116 track 8 decrement 60
D1(config-if)exit
D1(config-if)interface vlan 102
D1(config-if)standby version 2
^
% Invalid input detected at '^' marker.

D1(config-if)#standby 126 priority 150
D1(config-if)standby 126 preempt
D1(config-if)standby 126 track 8 decrement 60
D1(config-if)exit
D1(config)end
*Nov 20 07:41:12.530: %HSRP-5-STATECHANGE: Vlan100 Grp 104 state Standby -> Active
D1(config)#
*Nov 20 07:42:19.300: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
D1(config)end
*Nov 20 07:42:19.996: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
D1(config)end

```

Figura 25. Configurar la redundancia del primer salto Switch D1 Task 4.1 – 4.4

```

D1#  

D1#  

D1#  

D1#  

*Nov 20 08:01:13.769: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/2 (not full duplex), with R1 Ethernet1/2 (full duplex).
D1#  

D1#show standby brief  

   P indicates configured to preempt.

Interface  Grp  Mdl | State  Active      Standby          Virtual IP
V1100     104  90  P Active local      10.27.100.2    10.27.100.254
V1100     105  158 P Init   FEB8:D2:2       unknown        FE80::5:173FF:FEA0:6A
V1101     114  48  P Init   unknown      unknown        10.27.101.254
V1101     116  100 P Init   unknown      unknown        FE80::5:173FF:FEA0:74
V1102     124  90  P Init   unknown      unknown        10.27.102.254
D1#

```

© 2019 SolarWinds Worldwide, LLC

Figura 26. Verificación configurar la redundancia del primer salto Switch D1 Task 4.1 – 4.4

Switch D2:

```

ip sla 4
icmp-echo 10.0.11.1
frequency
exit
ip sla 6
icmp-echo 2001:db8:100:1011::1
frequency
exit
ip sla schedule 4 life forever start-time now


```

```
ip sla schedule 6 life forever start-time now
track 4 ip sla 4
delay down 10 up 15
exit
track 6 ip sla 6
delay down 10 up 15
exit
interface vlan 100
standby version 2
standby 104 ip 10.0.100.254
standby 104 preempt
standby 104 track 4 decrement 60
standby 106 ipv6 autoconfig
standby 106 priority 150
standby 106 preempt
standby 106 track 6 decrement 60
exit
interface vlan 101
standby version 2
standby 114 ip 10.0.101.254
standby 114 preempt
standby 114 track 4 decrement 60
standby 116 ipv6 autoconfig
standby 116 preempt
standby 116 track 6 decrement 60
exit
interface vlan 102
standby version 2
standby 124 ip 10.0.102.254
standby 124 priority 150
standby 124 preempt
standby 124 track 4 decrement 60
standby 126 ipv6 autoconfig
standby 126 priority 150
standby 126 preempt
```

```
standby 126 track 6 decrement 60
```

```
exit
```

```
end
```



```
D2#Config#  
Nov 20 07:58:49.661: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/0 (not full duplex), with R3 Ethernet1/0 (full duplex).  
D2#Config-ip-sla-echo 4  
D2#Config-ip-sla-echo)icmp-echo 10.0.11.1  
    ^  
    % Invalid input detected at '^' marker.  
D2#Config-ip-sla-echo)frequency 5  
D2#Config-ip-sla-echo)exit  
D2#Config#ip sla 6  
D2#Config-ip-sla-echo)icmp-echo 2001:db8:100:1011::1  
    ^  
    % Invalid input detected at '^' marker.  
D2#Config-ip-sla-echo)frequency 5  
D2#Config-ip-sla-echo)exit  
D2#Config#sla scheduled 6 life forever start-time now  
D2#Config#ip sla-echo 6 life forever start-time now  
D2#Config#track 4 ip sla 4  
D2#Config#track)delay down 18 up 15  
D2#Config#track)exit  
D2#Config#interface Vlan 100  
D2#Config#interface version 2  
D2#Config-if)#standby 104 in 10.27.100.254  
D2#Config-if)#standby 104 preempt  
D2#Config-if)#standby 104 track 4 decrement 60  
D2#Config-if)#standby 106 ipv6 autoconfig  
D2#Config-if)#standby 106 preempt  
D2#Config-if)#standby 108 track 6 decrement 60  
D2#Config-if)exit  
D2#Config#interface Vlan 101  
D2#Config-if)#standby version 2  
D2#Config-if)#standby 114 ip 10.27.101.254  
D2#Config-if)#standby 114 priority 158  
D2#Config-if)#standby 114 preempt  
D2#Config-if)#standby 114 track 4 decrement 60  
D2#Config-if)#standby 116 ipv6 autoconfig  
D2#Config-if)#standby 116 priority 150  
D2#Config-if)#standby 116 preempt  
D2#Config-if)#standby 116 track 6 decrement 60  
D2#Config-if)exit  
D2#Config#interface Vlan 102  
D2#Config#interface version 2  
D2#Config-if)#standby 124 ip 10.27.102.254  
D2#Config-if)#standby 124 preempt  
D2#Config-if)#standby 124 track 4 decrement 60  
D2#Config-if)#standby 126 ipv6 autoconfig  
D2#Config-if)#standby 126 preempt  
D2#Config-if)#standby 126 track 6 decrement 60  
D2#Config-if)exit  
D2#Config#end  
D2#  
Nov 20 07:58:49.661: NSYS-5-CONFIG_I: Configured from console by console  
D2#  
Nov 20 07:59:09.926: %HSRP-5-STATECHANGE: Vlan102 Grp 126 state Standby -> Active  
D2#  
Nov 20 07:59:36.987: %CDP-4-DUPLEX_MISMATCH: duplex mismatch discovered on Ethernet1/0 (not full duplex), with R3 Ethernet1/0 (full duplex).  
D2#
```

solarwinds  | Solar-PuTTY free tool

© 2019 SolarWinds Worldwide, LLC




Figura 27. Configurar la redundancia del primer salto Switch D2 Task 4.1 – 4.4

CONCLUSIONES

Por medio del desarrollo de la evaluación de habilidades ENCOR – Escenario 1 y Escenario 2 se comprendió como se implementa y configura una red de capa 2 implementando direccionamiento de la interfaz y proporcionando compatibilidad con los host, para esto utilizando protocolos de configuración de enrutamiento y configurando la redundancia del primer salto la cual es la capacidad que tiene una red para recuperarse dinámicamente de la falla de un dispositivo que funciona como Gateway predeterminado.

Se reforzó diversos conocimientos adquiridos a través de la realización de las guías y laboratorios desarrollados durante el transcurso del curso Diplomado de profundización cisco CCNP y la solución de las lecciones evacuativas en el entornode cisco (Netacad).

Con el desarrollo adecuada de la evaluación de habilidades ENCOR escenario 1, se pudo completar la configuración de la red para que hubiera accesibilidad completa de extremo a extremo, y para que los hosts tuvieran soporte de puerta de enlace predeterminada confiable y para que los protocolos de administración fueran operativos dentro de la parte de "Red de la empresa" de la topología. Se verifico que sus configuraciones cumplieron con las especificaciones proporcionadas y que los dispositivos funcionaran según lo requerido.

Con el desarrollo adecuado de la evaluación de habilidades ENCOR escenario 2, se pudo completar la configuración de protocolos de enrutamiento y se configuro los protocolos de enrutamiento IPv4 e IPv6. Al final de esta parte se verifico que la red estuviera completamente convergente. Los pings de IPv4 e IPv6 a la interfaz Loopback 0 desde D1 y D2 fueron exitosos.

BIBLIOGRAFÍA

- FROOM, R., FRAHIM, E. (2015). CISCO Press (Ed). Spanning Tree Implementation. Implementing Cisco IP Switched Networks (SWITCH) Foundation Learning Guide CCNP SWITCH 300-115. <https://1drv.ms/b/s!AmIjYei-NT1InWR0hoMxgBNv1CJ>
- TEARE, D., VACHON B., GRAZIANI, R. (2015). CISCO Press (Ed). EIGRP Implementation. Implementing Cisco IP Routing (ROUTE) Foundation Learning Guide CCNP ROUTE 300-101. <https://1drv.ms/b/s!AmIjYei-NT1InMfy2rhPZHwEoWx>
- Froom, R., Frahim, E. (2015). CISCO Press (Ed). First Hop Redundancy Protocols. Implementing Cisco IP Switched Networks (SWITCH) Foundation Learning Guide CCNP SWITCH 300-115. Recuperado de <https://1drv.ms/b/s!AmIjYei-NT1InWR0hoMxgBNv1CJ>
- Froom, R., Frahim, E. (2015). CISCO Press (Ed). v. Implementing Cisco IP Switched Networks (SWITCH) Foundation Learning Guide CCNP SWITCH 300-115. Recuperado de <https://1drv.ms/b/s!AmIjYei-NT1InWR0hoMxgBNv1CJ>