

**SOLUCIÓN DE DOS CASOS DE ESTUDIO, BAJO EL USO DE TECNOLOGÍA
CISCO**

**HENRY ALBERTO AMÉZQUITA CORREA
FRANK SINISTERRA NEIVA**

**UNIVERSIDAD NACIONAL ABIERTA Y A DISTANCIA “UNAD”
ESCUELA DE CIENCIAS BASICAS DE INGENIERIA
CURSO DE PROFUNDIZACIÓN CISCO
PALMIRA
2011**

**SOLUCIÓN DE DOS CASOS DE ESTUDIO, BAJO EL USO DE TECNOLOGÍA
CISCO**

**HENRY ALBERTO AMÉZQUITA CORREA
FRANK SINISTERRA NEIVA**

Monografía para optar el título de Ingeniero de Sistemas

TUTORES:

Yhon Jerson Robles Puentes

Ingeniero

Juan Carlos Vesga

Ingeniero

**UNIVERSIDAD NACIONAL ABIERTA Y A DISTANCIA “UNAD”
ESCUELA DE CIENCIAS BASICAS DE INGENIERIA
CURSO DE PROFUNDIZACIÓN CISCO
PALMIRA
2011**

TABLA DE CONTENIDO

	Pág.
LISTA DE TABLAS	5
LISTA DE GRÁFICAS	6
INTRODUCCION	7
OBJETIVOS	8
OBJETIVOS GENERALES.....	8
OBJETIVOS ESPECÍFICOS	8
1. CASO DE ESTUDIO CCNA1	9
1.1 DISPOSITIVOS A EMPLEAR.....	10
1.2 CONFIGURAR TOPOLOGÍA LÓGICA	10
1.3 CONFIGURAR TOPOLOGÍA FÍSICA	13
1.4 CONFIGURACION DE LOS ROUTERS	14
1.4.1 Router Bogotá.....	14
1.4.2 Router Bucaramanga.....	17
1.4.3 Router Pasto	22
1.5 CONFIGURACIÓN DE SWITCHES BOGOTÁ.....	26
1.5.1 Switch – Ingeniería.....	26
1.5.2 Switch –R y C	29
1.6 CONFIGURACIÓN DE SWITCHES BUCARAMANGA.....	32
1.6.1 Switch – Biblioteca	32
1.6.2 Switch – Administración	35
1.7 CONFIGURACIÓN DE SWITCH PASTO.....	38
1.7.1 Switch Pasto	38
1.8 CONFIGURACIÓN PROTOCOLO RIP EN TODOS LOS ROUTERS.....	42
1.9 PRUEBAS DE CONECTIVIDAD DE LA RED.....	43
1.9.1 Prueba de envío de mensajes	43

2.	CASO DE ESTUDIO CCNA2	47
2.1	DISEÑO CON ESPECIFICACIONES ACTUALES	49
2.2	DIRECCIONAMIENTO CON VLSM	55
2.3	CONFIGURACION DE LOS ROUTERS	57
	2.3.1 Configuración para sistema actual	57
	2.3.2 Configuración sistema con vlsm	63
3.	CONCLUSIONES.....	71
	BIBLIOGRAFIA.....	72

LISTA DE TABLAS

Pág.

Tabla 1. Tabla de direccionamiento LAN-----	11
Tabla 2. Tabla de direccionamiento WAN Bogotá - Bucaramanga-----	11
Tabla 3. Tabla de direccionamiento WAN Bogotá - Pasto-----	11
Tabla 4. Tabla de direccionamiento WAN Pasto - Bucaramanga-----	12
Tabla 5. Tabla de direccionamiento de Puertos - Bogotá-----	12
Tabla 6. Tabla de direccionamiento de Puertos - Bucaramanga-----	13
Tabla 7. Tabla de direccionamiento de Puertos – Pasto-----	13
Tabla 8. Tabla sede principal Pasto-----	49
Tabla 9. Tabla sede Bogotá-----	50
Tabla 10. Tabla sede Medellín-----	50
Tabla 11. Tabla sede Pereira-----	50
Tabla 12. Tabla sede Cali-----	51
Tabla 13. Tabla sede Cartagena-----	51
Tabla 14. Tabla sede Ibagué-----	51
Tabla 15. Tabla sede Cúcuta-----	52
Tabla 16. Tabla sede Bucaramanga-----	52
Tabla 17. Tabla sede Barranquilla-----	52
Tabla 18. Tabla sede Villavicencio-----	53
Tabla 19. Tabla sede Bogotá - VLSM-----	55
Tabla 20. Tabla sede Medellín - VLSM-----	55
Tabla 21. Tabla sede Pereira - VLSM-----	55
Tabla 22. Tabla sede Cali - VLSM-----	56
Tabla 23. Tabla sede Cartagena - VLSM-----	56
Tabla 24. Tabla sede Ibagué - VLSM-----	56
Tabla 25. Tabla sede Cúcuta - VLSM-----	56
Tabla 26. Tabla sede Bucaramanga - VLSM-----	57
Tabla 27. Tabla sede Barranquilla - VLSM-----	57
Tabla 28. Tabla sede Villavicencio - VLSM-----	57

LISTA DE GRÁFICAS

Pág.

Ilustración 1. Adición de módulo WIC-2T-----	9
Ilustración 2. Dispositivos a emplear -----	10
Ilustración 3. Configurar topología física -----	13
Ilustración 4. Prueba envío de mensajes-----	43
Ilustración 5. Prueba envío de mensajes-----	43
Ilustración 6. Ping PC1-Pasto a PC1-Ing-----	44
Ilustración 7. Ping PC5-Pasto a PC1-Biblioteca -----	44
Ilustración 8. Ping PC1-Biblioteca a PC1-Pasto -----	45
Ilustración 9. Ping PC1-Biblioteca a Router Pasto -----	45
Ilustración 10. Tracert PC10-RyC a Router-Bucaramanga -----	46
Ilustración 11. Tracert PC1-Ing a PC1-Biblioteca -----	46

INTRODUCCION

En el CCNA1, la práctica consiste en configurar tres routers ubicado en las ciudades de Bogotá, Bucaramanga y Pasto, cada una de estas ciudades representa una sede, cada una de las sedes consta de una distribución específica de acuerdo a los datos suministrados en la guía.

Para la realización de la práctica se debe tener en cuenta todo lo realizado en las prácticas y/o laboratorios anteriores para poder llevar a buen término la red, puntos como el subneteo, cables a utilizar, equipos de comunicación, etc., son de fundamental cuidado.

En lo que se refiere a CCNA2 se iniciará manifestando que para que un dispositivo de capa tres pueda determinar la ruta hacia un destino debe tener conocimiento de cómo hacerlo. Por eso se utilizarán:

Rutas estáticas: Aprendidas por el router a través del administrador, que establece dicha ruta manualmente, quien también debe actualizar cuando tenga lugar un cambio en la topología. Rutas dinámicas: Rutas aprendidas automáticamente por el router a través de la información enviada por otros routers, una vez que el administrador ha configurado un protocolo de enrutamiento que permite el aprendizaje dinámico de rutas. Para poder enrutar paquetes de información un router debe conocer lo siguiente:

La información de enrutamiento que el router aprende desde sus fuentes de enrutamiento se coloca en su propia tabla de enrutamiento. La tabla de enrutamiento es la fuente principal de información del router acerca de las redes. Si la red de destino está conectada directamente, el router ya sabrá el puerto que debe usar para reenviar paquetes. Si las redes de destino no están conectados directamente, el router debe aprender y calcular la ruta más óptima a usar para reenviar paquetes a dichas redes. La tabla de enrutamiento se construye manualmente por medio del administrador de la red y/o procesos dinámicos que se ejecutan en la red.

En este contexto se dará solución a una empresa que cuenta con una sede principal en diferentes ciudades del país aplicando enrutamiento con clase y enrutamiento sin clase como lo explica la guía con diferentes tipos de enrutamiento con el fin de ejercitar y practicar los contenidos de todo el curso.

OBJETIVOS

OBJETIVOS GENERALES

- En CCNA1 diseñar y configurar por medio del packet tracer una red que cumpla ciertos requerimientos y por supuesto halla conectividad en toda la red.
- Diseñar todo el esquema de enrutamiento para la topología acorde a las pautas establecidas en el documento Caso de estudio CCNA 2 exploración. Este diseño se debe realizar documentando cada uno de los pasos que se desarrollaron para alcanzar el objetivo.

OBJETIVOS ESPECÍFICOS

- Diseñar y documentar un esquema de direccionamiento según los requisitos.
- Aplicar una configuración básica a los dispositivos.
- Configurar una prioridad de Routers y RIP.
- Verificar la conectividad entre todos los dispositivos de la topología de la red.

1. CASO DE ESTUDIO CCNA1

Se analizará cada sede con el fin de tomar las decisiones y elegir la mejor la estructura de la red.

De acuerdo a la solicitud de la guía, se da inicio al estudio de las sedes en forma jerárquica, basándonos en el número de equipos (Host), quedando en su orden así.

**Bucaramanga: Switch1: Biblioteca. Switch2: Administración
15 hosts**

**Bogotá: Switch1: Ingeniera, Switch2: RyC
10 hosts**

**Pasto: Switch1: Spasto
5 hosts**

El router de Bogotá será quien maneje la sincronización (adicionar clockrate)

Se les adiciona a los tres routers el módulo WIC-2T para poder conectar los routers entre ellos.



Ilustración 1. Adición de módulo WIC-2T

1.1 DISPOSITIVOS A EMPLEAR




Ilustración 2. Dispositivos a emplear

1.2 CONFIGURAR TOPOLOGÍA LÓGICA

Se inicia con la dirección ip 192.172.10.0 y se procede a realizar el subneteo dependiendo de la cantidad de hosts a utilizar por cada subred. Entonces como para Bucaramanga son 15 hosts se toma una máscara de subred /27 y el número máximo de hosts es de 30 es decir se podría en un futuro adicionar 15 equipos más por subred. En esta ciudad se pueden formar 8 subredes.

Para Bogotá son 10 hosts se toma una máscara de subred /28 y el número máximo de hosts es de 14 es decir se podría en un futuro adicionar 4 equipos más por subred. En esta ciudad se pueden formar 16 subredes.

Para Pasto son 5 hosts se toma una máscara de subred /29 y el número máximo de hosts es de 6 es decir se podría en un futuro adicionar 1 equipo más por subred. En esta ciudad se pueden formar 32 subredes.

Se tabulan los datos para una mejor lectura:

TABLA DE DIRECCIONAMIENTO LAN

DESCRIPCION	B/MANGA - LAN 1 BIBLIOT	B/MANGA - LAN 2 ADMIN	BOGOTA - LAN 1 ING	BOGOTA - LAN 2 - RYC	PASTO - LAN
Dirección R	192.172.10.0	192.172.10.32	192.172.10.64	192.172.10.96	192.172.10.96
Gateway	192.172.10.29	192.172.10.61	192.172.10.77	192.172.10.93	192.172.10.101
IP PC1	192.172.10.1	192.172.10.33	192.172.10.65	192.172.10.81	192.172.10.97
IP ultimo PC	192.172.10.30	192.172.10.62	192.172.10.78	192.172.10.94	192.172.10.102
Dirección broadcast	192.172.10.31	192.172.10.63	192.172.10.79	192.172.10.95	192.172.10.103
Mascara	255.255.255.224	255.255.255.24	255.255.255.240	255.255.255.240	255.255.255.248

Tabla 1. Tabla de direccionamiento LAN

TABLA DE DIRECCIONAMIENTO WAN BOGOTÁ – BUCARAMANGA

DESCRIPCION	ENLACE B/GOTA-B/MANGA
Dirección de red	192.172.10.104
Serial Ser 0/0/1 (BOGOTA)	192.172.10.105
Serial Ser 0/1/1 (B/MANGA)	192.172.10.106
Dirección broadcast	192.172.10.107
Mascara de subred	255.255.255.252

Tabla 2. Tabla de direccionamiento WAN Bogotá - Bucaramanga

TABLA DE DIRECCIONAMIENTO WAN BOGOTÁ – PASTO

DESCRIPCION	ENLACE PASTO-B7GOTA
Dirección de red	192.172.10.112
Serial Ser 0/0/0 (BOGOTÁ)	192.172.10.113
Serial Ser 0/0/0 (PASTO)	192.172.10.114
Dirección broadcast	192.172.10.115
Mascara de subred	255.255.255.252

Tabla 3. Tabla de direccionamiento WAN Bogotá - Pasto

TABLA DE DIRECCIONAMIENTO WAN PASTO – BUCARAMANGA

DESCRIPCION	ENLACE B/MANGA-PASTO
Dirección de red	192.172.10.108
Serial Ser 0/0/1 (PASTO)	192.172.10.109
Serial Ser 0/1/0 (B/MANGA)	192.172.10.110
Dirección broadcast	192.172.10.111
Mascara de subred	255.255.255.252

Tabla 4. Tabla de direccionamiento WAN Pasto - Bucaramanga

TABLA DE DIRECCIONAMIENTO DE PUERTOS – BOGOTÁ

Dirección SubRed: (INGENIERÍAS) 192.172.10.64/28 y (R y C)192.172.10.96/28

DISPOSITIVO	Puertos	IP	Máscara subred	Gateway
PC1-ING	Fast Ethernet	192.172.10.65	255.255.255.240	192.172.10.77
PC10-RYC	Fast Ethernet	192.172.10.94	255.255.255.240	192.172.10.93
SWITCH-INGENIERIA	Fa 0/2	No aplica	No aplica	No aplica
	Fa 0/1	No aplica	No aplica	No aplica
SWITCH-RYC	Fa 0/2	No aplica	No aplica	No aplica
	Fa 0/1	No aplica	No aplica	No aplica
ROUTER	Fa 0/1 (RYC)	192.172.10.93	255.255.255.240	No aplica
	Fa 0/0 (ING)	192.172.10.77	255.255.255.240	No aplica

Tabla 5. Tabla de direccionamiento de Puertos - Bogotá

TABLA DE DIRECCIONAMIENTO DE PUERTOS – BUCARAMANGA

Dirección SubRed: (BIBLIOTECA) 192.172.10.0/27 y
(ADMINISTRACIÓN)192.172.10.32/27

DISPOSITIVO	Puertos	IP	Máscara subred	Gateway
PC1-BIBLIOTECA	Fast Ethernet	192.172.10.1	255.255.255.224	192.172.10.29
PC15-ADMIN	Fast Ethernet	192.172.10.62	255.255.255.224	192.172.10.61
SWITCH-BIBLIOTECA	Fa 0/2	No aplica	No aplica	No aplica
	Fa 0/1	No aplica	No aplica	No aplica
SWITCH-ADMIN	Fa 0/2	No aplica	No aplica	No aplica
	Fa 0/1	No aplica	No aplica	No aplica

ROUTER	Fa 0/0 (BIBLIOTECA)	192. 172.10.29	255.255.255.224	No aplica
	Fa 0/1 (ADMIN)	192. 172.10.61	255.255.255.224	No aplica

Tabla 6. Tabla de direccionamiento de Puertos - Bucaramanga

TABLA DE DIRECCIONAMIENTO DE PUERTOS – PASTO
Dirección SubRed: (PASTO) 192.172.10.96/29

DISPOSITIVO	Puertos	IP	Máscara subred	Gateway
PC1-PASTO	Fast Ethernet	192.172.10.97	255.255.255.248	192.172.10.101
PC5-PASTO	Fast Ethernet	192.172.10.102	255.255.255.248	192.172.10.101
SWITCH-SPASTO	Fa 0/1	No aplica	No aplica	No aplica
	Fa 0/2	No aplica	No aplica	No aplica
	Fa 0/3	No aplica	No aplica	No aplica
ROUTER	Fa 0/0	192. 172.10.101	255.255.255.248	No aplica

Tabla 7. Tabla de direccionamiento de Puertos – Pasto

1.3 CONFIGURAR TOPOLOGÍA FÍSICA




Ilustración 3. Configurar topología física

Cables utilizados.

- Cable de conexión directa
- Cable serial DCE

1.4 CONFIGURACION DE LOS ROUTERS

1.4.1 Router Bogotá

```
Router>enable
```

```
Router#configure terminal
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
Router(config)#interface FastEthernet0/0
```

```
Router(config-if)#no shutdown
```

```
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
```

```
Router(config-if)#ip address 192.172.10.77 255.255.255.240
```

```
Router(config-if)#
```

```
Router(config-if)#exit
```

```
Router(config)#interface FastEthernet0/1
```

```
Router(config-if)#no shutdown
```

```
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
```

```
Router(config)#interface FastEthernet0/1
```

```
Router(config-if)#ip address 192.172.10.93 255.255.255.240
```

```
Router(config)#interface Serial0/0/1
```

```
Router(config-if)#ip address 192.172.10.105 255.255.255.252
```

```
Router(config-if)#no shutdown
```

```
Router(config-if)#clock rate 9600
```

```
Router(config-if)#
```

```
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up
```

```
Router(config-if)#exit
```

```
Router(config)#interface Serial0/0/0
```

```
Router(config-if)#ip address 192.172.10.113 255.255.255.252
```

```

Router(config-if)#no shutdown
Router(config-if)#clock rate 9600
Router(config-if)#exit
Router(config)#hostname BOGOTA
BOGOTA(config)#enable secret CISCO
BOGOTA(config)#line con 0
BOGOTA(config-line)#password CISCO
BOGOTA(config-line)#login
BOGOTA(config-line)#line vty 0 4
BOGOTA(config-line)#password CISCO
BOGOTA(config-line)#login
BOGOTA(config-line)#banner motd %
Enter TEXT message. End with the character '%'.
ROUTER-BOGOTA %
BOGOTA(config)#interface fa0/0
BOGOTA(config-if)#description INTERFACE DE CONEXION CON LA RED DE
INGENIERIA
BOGOTA(config-if)#exit
BOGOTA(config)#interface fa0/1
BOGOTA(config-if)#description INTERFACE DE CONEXION CON LA RED DE
REGISTRO Y CONTROL
BOGOTA(config-if)#exit
BOGOTA(config)#exit
%SYS-5-CONFIG_I: Configured from console by console
BOGOTA#show interface fa0/0
FastEthernet0/0 is up, line protocol is up (connected)
  Hardware is Lance, address is 0004.9a8c.b101 (bia 0004.9a8c.b101)
Description: INTERFACE DE CONEXION CON LA RED DE INGENIERIA
Internet address is 192.172.10.77/28
  MTU 1500 bytes, BW 100000 Kbit, DLY 100 usec, rely 255/255, load 1/255
  Encapsulation ARPA, loopback not set
  ARP type: ARPA, ARP Timeout 04:00:00,
  Last input 00:00:08, output 00:00:05, output hang never
  Last clearing of "show interface" counters never
Queueing strategy: fifo
  Output queue :0/40 (size/max)
  5 minute input rate 0 bits/sec, 0 packets/sec
  5 minute output rate 0 bits/sec, 0 packets/sec
    0 packets input, 0 bytes, 0 no buffer

```

```

Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 input packets with dribble condition detected
0 packets output, 0 bytes, 0 underruns
0 output errors, 0 collisions, 1 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
BOGOTA#show interface fa0/1
FastEthernet0/1 is up, line protocol is up (connected)
Hardware is Lance, address is 0004.9a8c.b102 (bia 0004.9a8c.b102)
Description: INTERFACE DE CONEXION CON LA RED DE REGISTRO Y
CONTROL
Internet address is 192.172.10.93/28
MTU 1500 bytes, BW 100000 Kbit, DLY 100 usec, rely 255/255, load 1/255
Encapsulation ARPA, loopback not set
ARP type: ARPA, ARP Timeout 04:00:00,
Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
0 packets input, 0 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 input packets with dribble condition detected
0 packets output, 0 bytes, 0 underruns
0 output errors, 0 collisions, 1 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
BOGOTA#showip interface brief
Interface          IP-Address      OK? Method Status      Protocol

FastEthernet0/0    192.172.10.77  YES manual up          up

FastEthernet0/1    192.172.10.93  YES manual up          up

```



```

Serial0/0/0      192.172.10.113 YES manual up      up
Serial0/0/1      192.172.10.105 YES manual up      up

Vlan1           unassigned    YES manual administratively down down
BOGOTA#
BOGOTA#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
BOGOTA#
BOGOTA#config
Configuring from terminal, memory, or network [terminal]? terminal
Enter configuration commands, one per line. End with CNTL/Z.
BOGOTA(config)#
BOGOTA(config)#interface Serial0/0/0
BOGOTA(config-if)#description WAN BOGOTA-PASTO
BOGOTA(config-if)#no shutdown
BOGOTA(config-if)#exit
BOGOTA(config)#interface Serial0/0/1
BOGOTA(config-if)#description WAN BOGOTA-BUCARAMANGA
BOGOTA(config-if)#NO SHUTDOWN
BOGOTA(config-if)#interface fa0/0
BOGOTA(config-if)#no shutdown
BOGOTA(config-if)#interface fa0/1
BOGOTA(config-if)#no shutdown
BOGOTA(config-if)#
%SYS-5-CONFIG_I: Configured from console by console
BOGOTA#

```

1.4.2 Router Bucaramanga

```

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up
Router(config-if)#ip address 192.172.10.29 255.255.255.224
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/1
Router(config-if)#no shutdown
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed
state to up
Router(config-if)#shutdown

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to administratively
down
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed
state to down
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed
state to up
Router(config-if)#ip address 192.172.10.61 255.255.255.224
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1/1
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to upno shutdown
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed state
to upip address 192.172.10.106 255.255.255.224
Router(config-if)#ip address 192.172.10.106 255.255.255.252
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/1/0
Router(config-if)#ip address 192.172.10.110 255.255.255.252
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#exit
Router(config)#hostname BUCARAMANGA
```

```

BUCARAMANGA(config)#enablesecret CISCO
BUCARAMANGA(config)#line con 0
BUCARAMANGA(config-line)#password CISCO
BUCARAMANGA(config-line)#login
BUCARAMANGA(config-line)#line vty 0 4
BUCARAMANGA(config-line)#password CISCO
BUCARAMANGA(config-line)#login
BUCARAMANGA(config-line)#banner motd %
Enter TEXT message. End with the character '%'.
ROUTER-BMANGA%
BUCARAMANGA(config)#interface fa0/0
BUCARAMANGA(config-if)#description INTERFACE DE CONEXION CON LA
RED DE BIBLIOTECA
BUCARAMANGA(config-if)#no shutdown
BUCARAMANGA(config-if)#exit
BUCARAMANGA(config)#interface fa0/1
BUCARAMANGA(config-if)#description INTERFACE DE CONEXION CON LA
RED DE ADMINISTRACION
BUCARAMANGA(config-if)#no shutdown
BUCARAMANGA(config-if)#exit
BUCARAMANGA(config)#interface serial0/0/1
%Invalid interface type and number
BUCARAMANGA(config)#interface serial0/1/1
BUCARAMANGA(config-if)#description WAN BUCARAMANGA-BOGOTA
BUCARAMANGA(config-if)#no shutdown
BUCARAMANGA(config-if)#exit
BUCARAMANGA(config)#interface serial0/1/0
BUCARAMANGA(config-if)#description WAN BUCARAMANGA-PASTO
BUCARAMANGA(config-if)#no shutdown
BUCARAMANGA(config-if)#
BUCARAMANGA(config-if)#exit
BUCARAMANGA(config)#
%SYS-5-CONFIG_I: Configured from console by console
BUCARAMANGA#show interface fa0/1
FastEthernet0/1 is up, line protocol is up (connected)
  Hardware is Lance, address is 0002.4aec.be02 (bia 0002.4aec.be02)
  Description: INTERFACE DE CONEXION CON LA RED DE ADMINISTRACION
  Internet address is 192.172.10.61/27
    MTU 1500 bytes, BW 100000 Kbit, DLY 100 usec, rely 255/255, load 1/255

```

```

Encapsulation ARPA, loopback not set
ARP type: ARPA, ARP Timeout 04:00:00,
Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
0 packets input, 0 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 input packets with dribble condition detected
0 packets output, 0 bytes, 0 underruns
0 output errors, 0 collisions, 2 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
BUCARAMANGA#show interface fa0/0
FastEthernet0/0 is up, line protocol is up (connected)
Hardware is Lance, address is 0002.4aec.be01 (bia 0002.4aec.be01)
Description: INTERFACE DE CONEXION CON LA RED DE BIBLIOTECA
Internet address is 192.172.10.29/27
MTU 1500 bytes, BW 100000 Kbit, DLY 100 usec, rely 255/255, load 1/255
Encapsulation ARPA, loopback not set
ARP type: ARPA, ARP Timeout 04:00:00,
Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
0 packets input, 0 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 input packets with dribble condition detected
0 packets output, 0 bytes, 0 underruns
0 output errors, 0 collisions, 1 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier

```

0 output buffer failures, 0 output buffers swapped out
BUCARAMANGA#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	192.172.10.29	YES	manual	up	up
FastEthernet0/1	192.172.10.61	YES	manual	up	up
Serial0/1/0	192.172.10.110	YES	manual	up	down
Serial0/1/1	192.172.10.106	YES	manual	up	up
Vlan1	unassigned	YES	manual	administratively down	down

BUCARAMANGA#show interface serial0/1/1

Serial0/1/1 is up, line protocol is up (connected)

Hardware is HD64570

Description: WAN BUCARAMANGA-BOGOTA

Internet address is 192.172.10.106/30

MTU 1500 bytes, BW 1544 Kbit, DLY 20000 usec, rely 255/255, load 1/255

Encapsulation HDLC, loopback not set, keepalive set (10 sec)

Last input never, output never, output hang never

Last clearing of "show interface" counters never

Input queue: 0/75/0 (size/max/drops); Total output drops: 0

Queueing strategy: weighted fair

Output queue: 0/1000/64/0 (size/max total/threshold/drops)

Conversations 0/0/256 (active/max active/max total)

Reserved Conversations 0/0 (allocated/max allocated)

5 minute input rate 0 bits/sec, 0 packets/sec

5 minute output rate 0 bits/sec, 0 packets/sec

0 packets input, 0 bytes, 0 no buffer

Received 0 broadcasts, 0 runts, 0 giants, 0 throttles

0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort

0 packets output, 0 bytes, 0 underruns

0 output errors, 0 collisions, 1 interface resets

0 output buffer failures, 0 output buffers swapped out

0 carrier transitions

BUCARAMANGA#show interface serial0/1/0

Serial0/1/0 is up, line protocol is down (disabled)

Hardware is HD64570

```
Description: WAN BUCARAMANGA-PASTO
Internet address is 192.172.10.110/30
MTU 1500 bytes, BW 1544 Kbit, DLY 20000 usec, rely 255/255, load 1/255
Encapsulation HDLC, loopback not set, keepalive set (10 sec)
Last input never, output never, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0 (size/max/drops); Total output drops: 0
Queueing strategy: weighted fair
Output queue: 0/1000/64/0 (size/max total/threshold/drops)
Conversations 0/0/256 (active/max active/max total)
Reserved Conversations 0/0 (allocated/max allocated)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
0 packets input, 0 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 packets output, 0 bytes, 0 underruns
0 output errors, 0 collisions, 1 interface resets
0 output buffer failures, 0 output buffers swapped out
0 carrier transitions
DCD=up DSR=up DTR=up RTS=up CTS=up
BUCARAMANGA#
```

1.4.3 Router Pasto

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up
Router(config-if)#ip address 192.172.10.101 255.255.255.248
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0/0
Router(config-if)#ip address 192.172.10.114 255.255.255.252
```

```

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to upno shutdown
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state
to up
Router(config-if)#exit
Router(config)#interface Serial0/0/1
Router(config-if)#ip address 192.172.10.109 255.255.255.252
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to upno shutdown
Router(config-if)#exit
Router(config)#hostname PASTO
PASTO(config)#enable secret CISCO
PASTO(config)#line con 0
PASTO(config-line)#password CISCO
PASTO(config-line)#login
PASTO(config-line)#line vty 0 4
PASTO(config-line)#password CISCO
PASTO(config-line)#login
PASTO(config-line)#banner motd %
Enter TEXT message. End with the character '%'.
ROUTER-PASTO %
PASTO(config)#interface fa0/0
PASTO(config-if)#description INTERFACE DE CONEXION CON LA LAN DE
PASTO
PASTO(config-if)#no shutdown
PASTO(config-if)#exit
PASTO(config)#interface serial0/0/1
PASTO(config-if)#description WAN PASTO-BUCARAMANGA
PASTO(config-if)#no shutdown
PASTO(config-if)#exit
PASTO(config)#interface serial0/0/0
PASTO(config-if)#description WAN PASTO-BOGOTA
PASTO(config-if)#no shutdown
PASTO(config-if)#EXIT
PASTO(config)#exit
%SYS-5-CONFIG_I: Configured from console by console
PASTO#show interface fa0/0
FastEthernet0/0 is up, line protocol is up (connected)

```

```

Hardware is Lance, address is 0006.2ac4.8201 (bia 0006.2ac4.8201)
Description: INTERFACE DE CONEXION CON LA LAN DE PASTO
Internet address is 192.172.10.101/29
MTU 1500 bytes, BW 100000 Kbit, DLY 100 usec, rely 255/255, load 1/255
Encapsulation ARPA, loopback not set
ARP type: ARPA, ARP Timeout 04:00:00,
Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
0 packets input, 0 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 input packets with dribble condition detected
0 packets output, 0 bytes, 0 underruns
0 output errors, 0 collisions, 1 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
PASTO#show interface serial0/0/1
Serial0/0/1 is up, line protocol is down (disabled)
Hardware is HD64570
Description: WAN PASTO-BUCARAMANGA
Internet address is 192.172.10.109/30
MTU 1500 bytes, BW 1544 Kbit, DLY 20000 usec, rely 255/255, load 1/255
Encapsulation HDLC, loopback not set, keepalive set (10 sec)
Last input never, output never, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0 (size/max/drops); Total output drops: 0
Queueing strategy: weighted fair
Output queue: 0/1000/64/0 (size/max total/threshold/drops)
Conversations 0/0/256 (active/max active/max total)
Reserved Conversations 0/0 (allocated/max allocated)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
0 packets input, 0 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles

```



```

0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 packets output, 0 bytes, 0 underruns
0 output errors, 0 collisions, 1 interface resets
0 output buffer failures, 0 output buffers swapped out
0 carrier transitions
DCD=up DSR=up DTR=up RTS=up CTS=up
PASTO#show interface serial0/0/0
Serial0/0/0 is up, line protocol is up (connected)
Hardware is HD64570
Description: WAN PASTO-BOGOTA
Internet address is 192.172.10.114/30
MTU 1500 bytes, BW 1544 Kbit, DLY 20000 usec, rely 255/255, load 1/255
Encapsulation HDLC, loopback not set, keepalive set (10 sec)
Last input never, output never, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0 (size/max/drops); Total output drops: 0
Queueing strategy: weighted fair
Output queue: 0/1000/64/0 (size/max total/threshold/drops)
Conversations 0/0/256 (active/max active/max total)
Reserved Conversations 0/0 (allocated/max allocated)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
0 packets input, 0 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 packets output, 0 bytes, 0 underruns
0 output errors, 0 collisions, 1 interface resets
0 output buffer failures, 0 output buffers swapped out
0 carrier transitions
DCD=up DSR=up DTR=up RTS=up CTS=up

```

```
PASTO#showip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	192.172.10.101	YES	manual	up	up
FastEthernet0/1	unassigned	YES	manual	administratively down	down
Serial0/0/0	192.172.10.114	YES	manual	up	up

Serial0/0/1	192.172.10.109	YES	manual	up	down
Vlan1	unassigned	YES	manual	administratively	down

PASTO#

1.5 CONFIGURACIÓN DE SWITCHES BOGOTÁ

1.5.1 Switch – Ingeniería

```

Switch>enable
Switch#config
Configuring from terminal, memory, or network [terminal]? terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname INGENIERIA
INGENIERIA(config)#enable secret CISCO
INGENIERIA(config)#line con 0
INGENIERIA(config-line)#password CISCO
INGENIERIA(config-line)#login
INGENIERIA(config-line)#line vty 0 4
INGENIERIA(config-line)#password CISCO
INGENIERIA(config-line)#login
INGENIERIA(config-line)#banner motd %
Enter TEXT message. End with the character '%'.
LAN-INGENIERIA %
INGENIERIA(config)#INTERFACE fa0/2
INGENIERIA(config-if)#description INGENIERIA-HOST1
INGENIERIA(config-if)#no shutdown
INGENIERIA(config-if)#exit
INGENIERIA(config)#INTERFACE fa0/1
INGENIERIA(config-if)#description INGENIERIA-ROUTER
INGENIERIA(config-if)#NO SHUTDOWN
INGENIERIA(config-if)#exit
INGENIERIA(config)#exit
%SYS-5-CONFIG_I: Configured from console by console
INGENIERIA#showip interface brief
Interface          IP-Address      OK? Method Status      Protocol

```

FastEthernet0/1	unassigned	YES manual up	up
FastEthernet0/2	unassigned	YES manual up	up
FastEthernet0/3	unassigned	YES manual down	down
FastEthernet0/4	unassigned	YES manual down	down
FastEthernet0/5	unassigned	YES manual down	down
FastEthernet0/6	unassigned	YES manual down	down
FastEthernet0/7	unassigned	YES manual down	down
FastEthernet0/8	unassigned	YES manual down	down
FastEthernet0/9	unassigned	YES manual down	down
FastEthernet0/10	unassigned	YES manual down	down
FastEthernet0/11	unassigned	YES manual down	down
FastEthernet0/12	unassigned	YES manual down	down
FastEthernet0/13	unassigned	YES manual down	down
FastEthernet0/14	unassigned	YES manual down	down
FastEthernet0/15	unassigned	YES manual down	down
FastEthernet0/16	unassigned	YES manual down	down
FastEthernet0/17	unassigned	YES manual down	down
FastEthernet0/18	unassigned	YES manual down	down
FastEthernet0/19	unassigned	YES manual down	down
FastEthernet0/20	unassigned	YES manual down	down
FastEthernet0/21	unassigned	YES manual down	down
FastEthernet0/22	unassigned	YES manual down	down
FastEthernet0/23	unassigned	YES manual down	down
FastEthernet0/24	unassigned	YES manual down	down
GigabitEthernet1/1	unassigned	YES manual down	down
GigabitEthernet1/2	unassigned	YES manual down	down
Vlan1	unassigned	YES manual administratively down	down

INGENIERIA#show interface fa0/1

FastEthernet0/1 is up, line protocol is up (connected)

Hardware is Lance, address is 00d0.5835.3101 (bia 00d0.5835.3101)

Description: INGENIERIA-ROUTER

MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255

Encapsulation ARPA, loopback not set

Keepalive set (10 sec)

Full-duplex, 100Mb/s

input flow-control is off, output flow-control is off

ARP type: ARPA, ARP Timeout 04:00:00

Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
956 packets input, 193351 bytes, 0 no buffer
Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out

INGENIERIA#

INGENIERIA#show interface fa0/2

FastEthernet0/2 is up, line protocol is up (connected)

Hardware is Lance, address is 00d0.5835.3102 (bia 00d0.5835.3102)

Description: INGENIERIA-HOST1

MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255

Encapsulation ARPA, loopback not set

Keepalive set (10 sec)

Full-duplex, 100Mb/s

input flow-control is off, output flow-control is off

ARP type: ARPA, ARP Timeout 04:00:00

Last input 00:00:08, output 00:00:05, output hang never

Last clearing of "show interface" counters never

Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0

Queueing strategy: fifo

Output queue :0/40 (size/max)

5 minute input rate 0 bits/sec, 0 packets/sec

5 minute output rate 0 bits/sec, 0 packets/sec

956 packets input, 193351 bytes, 0 no buffer

Received 956 broadcasts, 0 runts, 0 giants, 0 throttles

0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort

```
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
INGENIERIA#
```

1.5.2 Switch –R y C

```
Switch>enable
Switch#config
Configuring from terminal, memory, or network [terminal]? terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname RYC
RYC(config)#enable secret CISCO
RYC(config)#line con 0
RYC(config-line)#password CISCO
RYC(config-line)#login
RYC(config-line)#line vty 0 4
RYC(config-line)#password CISCO
RYC(config-line)#login
RYC(config-line)#banner motd %
Enter TEXT message. End with the character '%'.
LAN-RYC %
RYC(config)#INTERFACE fa0/1
RYC(config-if)#descriptio RYC-ROUTER
RYC(config-if)#no shutdown
RYC(config-if)#exit
RYC(config)#INTERFACE fa0/2
RYC(config-if)#descriptio RYC-HOST10
RYC(config-if)#no shutdown
RYC(config-if)#exit
RYC(config)#exit
%SYS-5-CONFIG_I: Configured from console by console
RYC#showip interface brief
Interface          IP-Address      OK? Method Status          Protocol
```

FastEthernet0/1	unassigned	YES manual up	up
FastEthernet0/2	unassigned	YES manual up	up
FastEthernet0/3	unassigned	YES manual down	down
FastEthernet0/4	unassigned	YES manual down	down
FastEthernet0/5	unassigned	YES manual down	down
FastEthernet0/6	unassigned	YES manual down	down
FastEthernet0/7	unassigned	YES manual down	down
FastEthernet0/8	unassigned	YES manual down	down
FastEthernet0/9	unassigned	YES manual down	down
FastEthernet0/10	unassigned	YES manual down	down
FastEthernet0/11	unassigned	YES manual down	down
FastEthernet0/12	unassigned	YES manual down	down
FastEthernet0/13	unassigned	YES manual down	down
FastEthernet0/14	unassigned	YES manual down	down
FastEthernet0/15	unassigned	YES manual down	down
FastEthernet0/16	unassigned	YES manual down	down
FastEthernet0/17	unassigned	YES manual down	down
FastEthernet0/18	unassigned	YES manual down	down
FastEthernet0/19	unassigned	YES manual down	down
FastEthernet0/20	unassigned	YES manual down	down
FastEthernet0/21	unassigned	YES manual down	down
FastEthernet0/22	unassigned	YES manual down	down
FastEthernet0/23	unassigned	YES manual down	down
FastEthernet0/24	unassigned	YES manual down	down
GigabitEthernet1/1	unassigned	YES manual down	down
GigabitEthernet1/2	unassigned	YES manual down	down
Vlan1	unassigned	YES manual administratively down	down

RYC#show interface fa0/1

FastEthernet0/1 is up, line protocol is up (connected)

Hardware is Lance, address is 0010.1190.6401 (bia 0010.1190.6401)

Description: RYC-ROUTER

MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255

Encapsulation ARPA, loopback not set

Keepalive set (10 sec)

Full-duplex, 100Mb/s

input flow-control is off, output flow-control is off

ARP type: ARPA, ARP Timeout 04:00:00

Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
956 packets input, 193351 bytes, 0 no buffer
Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out

RYC#

RYC#show interface fa0/2

FastEthernet0/2 is up, line protocol is up (connected)

Hardware is Lance, address is 0010.1190.6402 (bia 0010.1190.6402)

Description: RYC-HOST10

MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255

Encapsulation ARPA, loopback not set

Keepalive set (10 sec)

Full-duplex, 100Mb/s

input flow-control is off, output flow-control is off

ARP type: ARPA, ARP Timeout 04:00:00

Last input 00:00:08, output 00:00:05, output hang never

Last clearing of "show interface" counters never

Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0

Queueing strategy: fifo

Output queue :0/40 (size/max)

5 minute input rate 0 bits/sec, 0 packets/sec

5 minute output rate 0 bits/sec, 0 packets/sec

956 packets input, 193351 bytes, 0 no buffer

Received 956 broadcasts, 0 runts, 0 giants, 0 throttles

0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort

```
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
RYC#
```

1.6 CONFIGURACIÓN DE SWITCHES BUCARAMANGA

1.6.1 Switch – Biblioteca

```
Switch>enable
Switch#config
Configuring from terminal, memory, or network [terminal]? terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname BIBLIOTECA
BIBLIOTECA(config)#enable secret CISCO
BIBLIOTECA(config)#line con 0
BIBLIOTECA(config-line)#password CISCO
BIBLIOTECA(config-line)#login
BIBLIOTECA(config-line)#line vty 0 4
BIBLIOTECA(config-line)#password CISCO
BIBLIOTECA(config-line)#login
BIBLIOTECA(config-line)#banner motd %
Enter TEXT message. End with the character '%'.
LAN-BIBLIOTECA %
BIBLIOTECA(config)#interface fa0/1
BIBLIOTECA(config-if)#description BIBLIOTECA-ROUTER
BIBLIOTECA(config-if)#no shutdown
BIBLIOTECA(config-if)#exit
BIBLIOTECA(config)#interface fa0/2
BIBLIOTECA(config-if)#description BIBLIOTECA-HOST1
BIBLIOTECA(config-if)#no shutdown
BIBLIOTECA(config-if)#exit
BIBLIOTECA(config)#exit
```


%SYS-5-CONFIG_I: Configured from console by console

BIBLIOTECA#showip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/1	unassigned	YES	manual	up	up
FastEthernet0/2	unassigned	YES	manual	up	up
FastEthernet0/3	unassigned	YES	manual	down	down
FastEthernet0/4	unassigned	YES	manual	down	down
FastEthernet0/5	unassigned	YES	manual	down	down
FastEthernet0/6	unassigned	YES	manual	down	down
FastEthernet0/7	unassigned	YES	manual	down	down
FastEthernet0/8	unassigned	YES	manual	down	down
FastEthernet0/9	unassigned	YES	manual	down	down
FastEthernet0/10	unassigned	YES	manual	down	down
FastEthernet0/11	unassigned	YES	manual	down	down
FastEthernet0/12	unassigned	YES	manual	down	down
FastEthernet0/13	unassigned	YES	manual	down	down
FastEthernet0/14	unassigned	YES	manual	down	down
FastEthernet0/15	unassigned	YES	manual	down	down
FastEthernet0/16	unassigned	YES	manual	down	down
FastEthernet0/17	unassigned	YES	manual	down	down
FastEthernet0/18	unassigned	YES	manual	down	down
FastEthernet0/19	unassigned	YES	manual	down	down
FastEthernet0/20	unassigned	YES	manual	down	down
FastEthernet0/21	unassigned	YES	manual	down	down
FastEthernet0/22	unassigned	YES	manual	down	down
FastEthernet0/23	unassigned	YES	manual	down	down
FastEthernet0/24	unassigned	YES	manual	down	down
GigabitEthernet1/1	unassigned	YES	manual	down	down
GigabitEthernet1/2	unassigned	YES	manual	down	down
Vlan1	unassigned	YES	manual	administratively down	down

BIBLIOTECA#show interface fa0/1

FastEthernet0/1 is up, line protocol is up (connected)

Hardware is Lance, address is 0000.0ccb.ae01 (bia 0000.0ccb.ae01)

Description: BIBLIOTECA-ROUTER

MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255

Encapsulation ARPA, loopback not set

Keepalive set (10 sec)

```
Full-duplex, 100Mb/s
input flow-control is off, output flow-control is off
ARP type: ARPA, ARP Timeout 04:00:00
Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
956 packets input, 193351 bytes, 0 no buffer
Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
```

BIBLIOTECA#

BIBLIOTECA#show interface fa0/2

FastEthernet0/2 is up, line protocol is up (connected)

Hardware is Lance, address is 0000.0ccb.ae02 (bia 0000.0ccb.ae02)

Description: BIBLIOTECA-HOST1

MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255

Encapsulation ARPA, loopback not set

Keepalive set (10 sec)

Full-duplex, 100Mb/s

input flow-control is off, output flow-control is off

ARP type: ARPA, ARP Timeout 04:00:00

Last input 00:00:08, output 00:00:05, output hang never

Last clearing of "show interface" counters never

Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0

Queueing strategy: fifo

Output queue :0/40 (size/max)

5 minute input rate 0 bits/sec, 0 packets/sec

```
5 minute output rate 0 bits/sec, 0 packets/sec
956 packets input, 193351 bytes, 0 no buffer
Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
BIBLIOTECA#
```

1.6.2 Switch – Administración

```
Switch>ENABLE
Switch#config
Configuring from terminal, memory, or network [terminal]? terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname ADMIN
ADMIN(config)#enable secret CISCO
ADMIN(config)#LINE CON 0
ADMIN(config-line)#password CISCO
ADMIN(config-line)#login
ADMIN(config-line)#line vty 0 4
ADMIN(config-line)#password CISCO
ADMIN(config-line)#login
ADMIN(config-line)#banner motd %
Enter TEXT message. End with the character '%'.
LAN-ADMIN%
ADMIN(config)#interface fa0/1
ADMIN(config-if)#description ADMIN-ROUTER
ADMIN(config-if)#no shutdown
ADMIN(config-if)#exit
ADMIN(config)#interface fa0/2
ADMIN(config-if)#description ADMIN-HOST15
ADMIN(config-if)#no shutdown
ADMIN(config-if)#exit
```

```
ADMIN(config)#exit
```

```
%SYS-5-CONFIG_I: Configured from console by console
```

```
ADMIN#showip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/1	unassigned	YES	manual	up	up
FastEthernet0/2	unassigned	YES	manual	up	up
FastEthernet0/3	unassigned	YES	manual	down	down
FastEthernet0/4	unassigned	YES	manual	down	down
FastEthernet0/5	unassigned	YES	manual	down	down
FastEthernet0/6	unassigned	YES	manual	down	down
FastEthernet0/7	unassigned	YES	manual	down	down
FastEthernet0/8	unassigned	YES	manual	down	down
FastEthernet0/9	unassigned	YES	manual	down	down
FastEthernet0/10	unassigned	YES	manual	down	down
FastEthernet0/11	unassigned	YES	manual	down	down
FastEthernet0/12	unassigned	YES	manual	down	down
FastEthernet0/13	unassigned	YES	manual	down	down
FastEthernet0/14	unassigned	YES	manual	down	down
FastEthernet0/15	unassigned	YES	manual	down	down
FastEthernet0/16	unassigned	YES	manual	down	down
FastEthernet0/17	unassigned	YES	manual	down	down
FastEthernet0/18	unassigned	YES	manual	down	down
FastEthernet0/19	unassigned	YES	manual	down	down
FastEthernet0/20	unassigned	YES	manual	down	down
FastEthernet0/21	unassigned	YES	manual	down	down
FastEthernet0/22	unassigned	YES	manual	down	down
FastEthernet0/23	unassigned	YES	manual	down	down
FastEthernet0/24	unassigned	YES	manual	down	down
GigabitEthernet1/1	unassigned	YES	manual	down	down
GigabitEthernet1/2	unassigned	YES	manual	down	down
Vlan1	unassigned	YES	manual	administratively down	down

```
ADMIN#show interface fa0/1
```

```
FastEthernet0/1 is up, line protocol is up (connected)
```

```
Hardware is Lance, address is 0002.16e8.2c01 (bia 0002.16e8.2c01)
```

```
Description: ADMIN-ROUTER
```

```
MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,  
reliability 255/255, txload 1/255, rxload 1/255
```

```
Encapsulation ARPA, loopback not set
```

```
Keepalive set (10 sec)
  Full-duplex, 100Mb/s
input flow-control is off, output flow-control is off
  ARP type: ARPA, ARP Timeout 04:00:00
  Last input 00:00:08, output 00:00:05, output hang never
  Last clearing of "show interface" counters never
  Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: fifo
  Output queue :0/40 (size/max)
  5 minute input rate 0 bits/sec, 0 packets/sec
  5 minute output rate 0 bits/sec, 0 packets/sec
    956 packets input, 193351 bytes, 0 no buffer
    Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
    0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
    0 watchdog, 0 multicast, 0 pause input
    0 input packets with dribble condition detected
    2357 packets output, 263570 bytes, 0 underruns
    0 output errors, 0 collisions, 10 interface resets
    0 babbles, 0 late collision, 0 deferred
    0 lost carrier, 0 no carrier
    0 output buffer failures, 0 output buffers swapped out
```

```
ADMIN#show interface fa0/2
```

```
FastEthernet0/2 is up, line protocol is up (connected)
  Hardware is Lance, address is 0002.16e8.2c02 (bia 0002.16e8.2c02)
  Description: ADMIN-HOST15
  MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255
  Encapsulation ARPA, loopback not set
```

```
Keepalive set (10 sec)
  Full-duplex, 100Mb/s
input flow-control is off, output flow-control is off
  ARP type: ARPA, ARP Timeout 04:00:00
  Last input 00:00:08, output 00:00:05, output hang never
  Last clearing of "show interface" counters never
  Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: fifo
  Output queue :0/40 (size/max)
  5 minute input rate 0 bits/sec, 0 packets/sec
  5 minute output rate 0 bits/sec, 0 packets/sec
```

```
956 packets input, 193351 bytes, 0 no buffer
Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
ADMIN#
```

1.7 CONFIGURACIÓN DE SWITCH PASTO

1.7.1 Switch Pasto

```
Switch>enable
Switch#config
Configuring from terminal, memory, or network [terminal]? terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname SPASTO
SPASTO(config)#enable secret CISCO
SPASTO(config)#line con 0
SPASTO(config-line)#password CISCO
SPASTO(config-line)#login
SPASTO(config-line)#line vty 0 4
SPASTO(config-line)#password CISCO
SPASTO(config-line)#login
SPASTO(config-line)#banner motd %
Enter TEXT message. End with the character '%'.
LAN-SPASTO %
SPASTO(config)#INTERFACE fa0/1
SPASTO(config-if)#description SPASTO-ROUTER
SPASTO(config-if)#no shutdown
SPASTO(config-if)#exit
SPASTO(config)#INTERFACE fa0/2
SPASTO(config-if)#description SPASTO-HOST1
SPASTO(config-if)#no shutdown
```

```

SPASTO(config-if)#exit
SPASTO(config)#INTERFACE fa0/3
SPASTO(config-if)#description SPASTO-HOST5
SPASTO(config-if)#no shutdown
SPASTO(config-if)#exit
SPASTO(config)#exit
SPASTO(config)#exit
%SYS-5-CONFIG_I: Configured from console by console
SPASTO#showip interface brief

```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/1	unassigned	YES	manual	up	up
FastEthernet0/2	unassigned	YES	manual	up	up
FastEthernet0/3	unassigned	YES	manual	up	up
FastEthernet0/4	unassigned	YES	manual	down	down
FastEthernet0/5	unassigned	YES	manual	down	down
FastEthernet0/6	unassigned	YES	manual	down	down
FastEthernet0/7	unassigned	YES	manual	down	down
FastEthernet0/8	unassigned	YES	manual	down	down
FastEthernet0/9	unassigned	YES	manual	down	down
FastEthernet0/10	unassigned	YES	manual	down	down
FastEthernet0/11	unassigned	YES	manual	down	down
FastEthernet0/12	unassigned	YES	manual	down	down
FastEthernet0/13	unassigned	YES	manual	down	down
FastEthernet0/14	unassigned	YES	manual	down	down
FastEthernet0/15	unassigned	YES	manual	down	down
FastEthernet0/16	unassigned	YES	manual	down	down
FastEthernet0/17	unassigned	YES	manual	down	down
FastEthernet0/18	unassigned	YES	manual	down	down
FastEthernet0/19	unassigned	YES	manual	down	down
FastEthernet0/20	unassigned	YES	manual	down	down
FastEthernet0/21	unassigned	YES	manual	down	down
FastEthernet0/22	unassigned	YES	manual	down	down
FastEthernet0/23	unassigned	YES	manual	down	down
FastEthernet0/24	unassigned	YES	manual	down	down
GigabitEthernet1/1	unassigned	YES	manual	down	down
GigabitEthernet1/2	unassigned	YES	manual	down	down
Vlan1	unassigned	YES	manual	administratively down	down

```

SPASTO#show interface fa0/1
FastEthernet0/1 is up, line protocol is up (connected)

```

Hardware is Lance, address is 0001.c7e0.ed01 (bia 0001.c7e0.ed01)
Description: SPASTO-ROUTER
MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255
Encapsulation ARPA, loopback not set
Keepalive set (10 sec)
Full-duplex, 100Mb/s
input flow-control is off, output flow-control is off
ARP type: ARPA, ARP Timeout 04:00:00
Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
956 packets input, 193351 bytes, 0 no buffer
Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out

SPASTO#

SPASTO#show interface fa0/2

FastEthernet0/2 is up, line protocol is up (connected)

Hardware is Lance, address is 0001.c7e0.ed02 (bia 0001.c7e0.ed02)

Description: SPASTO-HOST1

MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255

Encapsulation ARPA, loopback not set

Keepalive set (10 sec)

Full-duplex, 100Mb/s

input flow-control is off, output flow-control is off

ARP type: ARPA, ARP Timeout 04:00:00

Last input 00:00:08, output 00:00:05, output hang never


```

Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
 956 packets input, 193351 bytes, 0 no buffer
Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
SPASTO#show interface fa0/3
FastEthernet0/3 is up, line protocol is up (connected)
Hardware is Lance, address is 0001.c7e0.ed03 (bia 0001.c7e0.ed03)
Description: SPASTO-HOST5
MTU 1500 bytes, BW 100000 Kbit, DLY 1000 usec,
reliability 255/255, txload 1/255, rxload 1/255
Encapsulation ARPA, loopback not set
Keepalive set (10 sec)
Full-duplex, 100Mb/s
input flow-control is off, output flow-control is off
ARP type: ARPA, ARP Timeout 04:00:00
Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
 956 packets input, 193351 bytes, 0 no buffer
Received 956 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
0 watchdog, 0 multicast, 0 pause input
0 input packets with dribble condition detected

```

```
2357 packets output, 263570 bytes, 0 underruns
0 output errors, 0 collisions, 10 interface resets
0 babbles, 0 late collision, 0 deferred
0 lost carrier, 0 no carrier
0 output buffer failures, 0 output buffers swapped out
SPASTO#
```

1.8 CONFIGURACIÓN PROTOCOLO RIP EN TODOS LOS ROUTERS

En todos los routers en el protocolo RIP se digita la dirección de red general que es 192.172.10.0.

```
BOGOTA(config)#
BOGOTA(config)#router rip
BOGOTA(config-router)#network 192.172.10.0
BOGOTA(config-router)#version 2
BOGOTA(config-router)#
```

```
PASTO(config)#
PASTO(config)#router rip
PASTO(config-router)#network 192.172.10.0
PASTO(config-router)#network 192.172.10.0
PASTO(config-router)#version 2
PASTO(config-router)#
```

```
BUCARAMANGA(config)#router rip
BUCARAMANGA(config-router)#
BUCARAMANGA(config-router)#exit
BUCARAMANGA(config)#router rip
BUCARAMANGA(config-router)#network 192.172.10.0
BUCARAMANGA(config-router)#version 2
BUCARAMANGA(config-router)#
```

1.9 PRUEBAS DE CONECTIVIDAD DE LA RED

1.9.1 Prueba de envío de mensajes

The screenshot shows a network simulation in Packet Tracer 5.0. The network topology includes several routers (1841, 2950T-24) and PCs (PC1-PASTO, PC5-PASTO, PC1-ING, PC10-RYC, PC1-BIBLIOTECA). A 'Lista de Eventos' (Event List) window is open, showing a list of captured events with columns for time, device, and type. The 'Simulación' (Simulation) window is also visible at the bottom.

Vis.	Tiempo(sec)	Último Dispositivo	En Dispositivo	Tipo	Ir
	3.470	--	SPASTO	STP	
	3.470	--	SPASTO	STP	
	3.470	--	SPASTO	STP	
	3.471	SPASTO	PASTO	STP	
	3.471	SPASTO	PC1-PASTO	STP	
	3.471	SPASTO	PC5-PASTO	STP	
	3.532	--	BIBLIOTECA	STP	
	3.532	--	BIBLIOTECA	STP	

Ilustración 5. Prueba envío de mensajes

The screenshot shows a network simulation in Packet Tracer 5.0. The network topology is similar to the previous screenshot. A table at the bottom shows the results of a connectivity test, listing source and destination devices, types, and times.

Lanzar	ÚltimoEstado	Fuente	Destino	Tipo	Color	Tiempo(sec)	Periódico	Num	Editar	Borrar
	Exitoso	PC15-ADMIN	PC5-PASTO	ICMP		0.000	N	0	(edit)	(delete)
	Exitoso	PC15-ADMIN	PASTO	ICMP		0.000	N	1	(edit)	(delete)
	Exitoso	PC1-ING	BUCARAMANGA	ICMP		0.000	N	2	(edit)	(delete)
	Exitoso	PC10-RYC	PC5-PASTO	ICMP		0.000	N	3	(edit)	(delete)
	Exitoso	PC1-BIBLIOTECA	PC10-RYC	ICMP		0.000	N	4	(edit)	(delete)
	Exitoso	BUCARAMANGA	PC1-PASTO	ICMP		0.000	N	5	(edit)	(delete)
	Exitoso	BOGOTÁ	PC15-ADMIN	ICMP		0.000	N	6	(edit)	(delete)
	Exitoso	PC10-RYC	PASTO	ICMP		0.000	N	7	(edit)	(delete)

Ilustración 4. Prueba envío de mensajes

A través de ping. Los siguientes son algunos de los pantallazos donde se prueba la conectividad de la red.

De PC1-PASTO a PC1-ING (PASTO – BOGOTA)

```
PC>ping 192.172.10.65

Pinging 192.172.10.65 with 32 bytes of data:

Reply from 192.172.10.65: bytes=32 time=87ms TTL=126
Reply from 192.172.10.65: bytes=32 time=39ms TTL=126
Reply from 192.172.10.65: bytes=32 time=44ms TTL=126
Reply from 192.172.10.65: bytes=32 time=38ms TTL=126

Ping statistics for 192.172.10.65:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 38ms, Maximum = 87ms, Average = 52ms
```

Ilustración 6. Ping PC1-Pasto a PC1-Ing

De PC5-PASTO a PC1-BIBLIOTECA (PASTO – BUCARAMANGA)

```
PC>ping 192.172.10.1

Pinging 192.172.10.1 with 32 bytes of data:

Reply from 192.172.10.1: bytes=32 time=72ms TTL=125
Reply from 192.172.10.1: bytes=32 time=41ms TTL=125
Reply from 192.172.10.1: bytes=32 time=54ms TTL=125
Reply from 192.172.10.1: bytes=32 time=35ms TTL=125

Ping statistics for 192.172.10.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 35ms, Maximum = 72ms, Average = 50ms
```

Ilustración 7. Ping PC5-Pasto a PC1-Biblioteca

De PC1-BIBLIOTECA a PC1-PASTO (BUCARAMANGA – PASTO)

```
PC>ping 192.172.10.97

Pinging 192.172.10.97 with 32 bytes of data:

Reply from 192.172.10.97: bytes=32 time=57ms TTL=125
Reply from 192.172.10.97: bytes=32 time=61ms TTL=125
Reply from 192.172.10.97: bytes=32 time=46ms TTL=125
Reply from 192.172.10.97: bytes=32 time=57ms TTL=125

Ping statistics for 192.172.10.97:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 46ms, Maximum = 61ms, Average = 55ms
```

Ilustración 8. Ping PC1-Biblioteca a PC1-Pasto

De PC1-BIBLIOTECA a ROUTER PASTO (BUCARAMANGA – PASTO)

```
PC>ping 192.172.10.101

Pinging 192.172.10.101 with 32 bytes of data:

Reply from 192.172.10.101: bytes=32 time=69ms TTL=253
Reply from 192.172.10.101: bytes=32 time=38ms TTL=253
Reply from 192.172.10.101: bytes=32 time=49ms TTL=253
Reply from 192.172.10.101: bytes=32 time=55ms TTL=253

Ping statistics for 192.172.10.101:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 38ms, Maximum = 69ms, Average = 52ms
```

Ilustración 9. Ping PC1-Biblioteca a Router Pasto

A través de tracert. A continuación se muestran algunos pantallazos.
De PC10-RYC a ROUTER-BUCARAMANGA (BOGOTÁ – BUCARAMANGA)

```
PC>tracert 192.172.10.29

Tracing route to 192.172.10.29 over a maximum of 30 hops:

  0  0 ms    0 ms    0 ms    192.172.10.1
  1  59 ms   8 ms    8 ms    192.172.10.93
  2  10 ms   13 ms   17 ms   192.172.10.29

Trace complete.
```

Ilustración 10. Tracert PC10-RyC a Router-Bucaramanga

De PC1-ING a PC1-BIBLIOTECA (BOGOTA – BUCARAMANGA)

```
PC>tracert 192.172.10.1

Tracing route to 192.172.10.1 over a maximum of 30 hops:

  0  21 ms   9 ms    6 ms    192.172.10.77
  1  13 ms   12 ms   19 ms   192.172.10.106
  2  18 ms   18 ms   26 ms   192.172.10.1

Trace complete.
```

Ilustración 11. Tracert PC1-Ing a PC1-Biblioteca

2. CASO DE ESTUDIO CCNA2

Una empresa con varias sucursales en diferentes ciudades del país desea modernizar el manejo de la red de datos que actualmente tiene y se describe a continuación:

Nombre empresa: CHALVER

Objeto social: Empresa dedicada a la exportación e importación de equipos de cómputo.

Sedes:

*Principal: Pasto

Sucursales

- Bogotá
- Medellín
- Pereira
- Cali
- Cartagena
- Ibagué
- Cúcuta
- Bucaramanga
- Barranquilla
- Villavicencio

Descripción Sede Principal:

Se cuenta con un edificio que tiene 3 pisos, en el primero están los cuartos de equipos que permiten la conexión con todo el país, allí se tiene:

- 3 Enrutadores CISCO principales, uno para el enlace nacional, otro para la administración de la red interna en los pisos 1 y 2 y otro para el tercer piso.
- 3 SwitchesCatalyst CISCO, uno para cada piso del edificio con soporte de 24 equipos cada uno, actualmente se está al 95% de la capacidad.
- Un canal dedicado con tecnología ATM que se ha contratado con ISP nacional de capacidad de 2048 Kbps.
- El direccionamiento a nivel local es clase C. Se cuenta con 70 equipos en tres pisos, se tiene las oficinas de Sistemas (15 equipos, primer piso), Gerencia (5 Equipos, primer

piso), Ventas (30 equipos, segundo piso), Importaciones (10 Equipos, tercer piso), Mercadeo (5 Equipos, tercer piso) y Contabilidad (5 Equipos, tercer piso)

- El direccionamiento a nivel nacional es Clase A privada, se tiene un IP pública al ISP para el servicio de Internet la cual es: 200.21.85.93 Mascara: 255.255.240.0.

- Actualmente el Enrutamiento se hace con RIP versión 1, tanto para la parte local como para la parte nacional.

Descripción de sucursales:

Cada sucursal se compone de oficinas arrendadas en un piso de un edificio y compone de los siguientes elementos:

- Dos Routers por sucursal: Uno para el enlace nacional y otro para la administración de la red interna.

- Un SwitchCatalyst para 24 equipos, actualmente se utilizan 20 puertos.

- Los 20 equipos se utilizan así: 10 para ventas, 5 para sistemas, 2 para importaciones y 3 para contabilidad.

- Un canal dedicado con tecnología ATM para conectarse a la sede principal de 512Kbps.

- El direccionamiento a nivel local es Clase C privado y a nivel nacional B como se había dicho en la descripción de la sede principal.

- El enrutamiento también es RIP.

Entonces:

1. Realizar el diseño de la sede principal y sucursales con las especificaciones actuales, un archivo PKT para la sede principal y para una sucursal.

2. Realizar un diseño a nivel de Routers y Switch para todo el país con PacketTracert.

3. Aplicar el direccionamiento especificado en el diseño del punto anterior.

4. Aplicar el enrutamiento actual en el diseño del punto 2.

5. Cambiar las especificaciones de direccionamiento y enrutamiento según las siguientes condiciones:

- Aplicar VLSM en la sede principal y sucursales, para la conexión nacional

- Aplicar Enrutamiento OSPF en la conexión Nacional, EIGRP para la conexión interna en la sede principal

- Aplicar Enrutamiento RIPv2 para todas las sucursales,

2.1 DISEÑO CON ESPECIFICACIONES ACTUALES

SEDE PRINCIPAL PASTO,
Subred direccionamiento nacional 10.0.0.0
Subred direccionamiento local 192.168.0.0

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
R NACIONAL	S0/0/0	200.21.85.93	255.255.240.0	N/A
	S0/0/1	192.168.3.98	255.255.255.224	N/A
	S0/1/0	10.3.0.1	255.255.0.0	N/A
	S0/1/1	10.4.0.1	255.255.0.0	N/A
	S0/2/0	10.1.0.1	255.255.0.0	N/A
	S0/2/1	10.2.0.1	255.255.0.0	N/A
	S0/3/0	10.5.0.1	255.255.0.0	N/A
	S0/3/1	10.6.0.1	255.255.0.0	N/A
	S1/0/0	10.7.0.1	255.255.0.0	N/A
	S1/0/1	10.8.0.1	255.255.0.0	N/A
	S1/1/0	10.9.0.1	255.255.0.0	N/A
	S1/1/1	10.10.0.1	255.255.0.0	N/A
	Fa0/1	192.168.3.130	255.255.255.224	N/A
R PISO 1 Y 2	Fa0/0	192.168.3.33	255.255.255.224	N/A
	Fa0/1	192.168.3.1	255.255.255.224	N/A
	S0/0/0	192.168.3.97	255.255.255.224	N/A
R PISO 3.	Fa0/0	192.168.3.65	255.255.255.224	N/A
	S0/0/1	192.168.3.129	255.255.255.224	N/A
Rango 15 PC Sistemas	NIC	192.168.3.2-192.168.3.16	255.255.255.224	192.168.3.1
Rango 5 PC Gerencia	NIC	192.168.3.17-192.168.3.21	255.255.255.224	192.168.3.1
Rango 24 PC Ventas	NIC	192.168.3.34-192.168.3.57	255.255.255.224	192.168.3.33
Rango 6 PC ventas	NIC	192.168.3.22-192.168.3.27	255.255.255.224	192.168.3.1
Rango PC piso 3	NIC	192.168.3.66-192.168.3.85	255.255.255.224	192.168.3.65

Tabla 8. Tabla sede principal Pasto

SEDE BOGOTA

Subred nacional 10.1.0.0

Subred local 192.168.4.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RBTA	S0/0/0	10.1.0.2	255.255.0.0	N/A
	S0/0/1	192.168.4.34	255.255.255.224	N/A
RLBTA	S0/0/0	192.168.4.33	255.255.255.224	N/A
	Fa0/0	192.168.4.1	255.255.255.224	N/A

Tabla 9. Tabla sede Bogotá

SEDE MEDELLIN

Subred nacional 10.2.0.0

Subred local 192.168.5.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RMED	S0/0/0	10.2.0.2	255.255.0.0	N/A
	S0/0/1	192.168.5.34	255.255.255.224	N/A
RLMED	S0/0/0	192.168.5.33	255.255.255.224	N/A
	Fa0/0	192.168.5.1	255.255.255.224	N/A

Tabla 10. Tabla sede Medellín

SEDE PEREIRA

Subred nacional 10.3.0.0

Subred local 192.168.6.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RPEREIRA	S0/0/0	10.3.0.2	255.255.0.0	N/A
	S0/0/1	192.168.6.34	255.255.255.224	N/A
RLPEREIRA	S0/0/0	192.168.6.33	255.255.255.224	N/A
	Fa0/0	192.168.6.1	255.255.255.224	N/A

Tabla 11. Tabla sede Pereira

SEDE CALI

Subred nacional 10.4.0.0

Subred local 192.168.7.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RCALI	S0/0/0	10.4.0.2	255.255.0.0	N/A
	S0/0/1	192.168.7.34	255.255.255.224	N/A
RLCALI	S0/0/0	192.168.7.33	255.255.255.224	N/A
	Fa0/0	192.168.7.1	255.255.255.224	N/A

Tabla 12. Tabla sede Cali

SEDE CARTAGENA

Subred nacional 10.5.0.0

Subred local 192.168.8.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RCARTAGENA	S0/0/0	10.5.0.2	255.255.0.0	N/A
	S0/0/1	192.168.8.34	255.255.255.224	N/A
RLCARTAGENA	S0/0/0	192.168.8.33	255.255.255.224	N/A
	Fa0/0	192.168.8.1	255.255.255.224	N/A

Tabla 13. Tabla sede Cartagena

SEDE IBAGUE

Subred nacional 10.6.0.0

Subred local 192.168.9.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RIBAGUE	S0/0/0	10.6.0.2	255.255.0.0	N/A
	S0/0/1	192.168.9.34	255.255.255.224	N/A
RLIBAGUE	S0/0/0	192.168.9.33	255.255.255.224	N/A
	Fa0/0	192.168.9.1	255.255.255.224	N/A

Tabla 14. Tabla sede Ibagué

SEDE CUCUTA

Subred nacional 10.7.0.0

Subred local 192.168.10.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RCUCUTA	S0/0/0	10.7.0.2	255.255.0.0	N/A
	S0/0/1	192.168.10.34	255.255.255.224	N/A
RCUCUTA	S0/0/0	192.168.10.33	255.255.255.224	N/A
	Fa0/0	192.168.10.1	255.255.255.224	N/A

Tabla 15. Tabla sede Cúcuta

SEDE BUCARAMANGA

Subred nacional 10.8.0.0

Subred local 192.168.11.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RBMANGA	S0/0/0	10.8.0.2	255.255.0.0	N/A
	S0/0/1	192.168.11.34	255.255.255.224	N/A
RLBUMANGA	S0/0/0	192.168.11.33	255.255.255.224	N/A
	Fa0/0	192.168.11.1	255.255.255.224	N/A

Tabla 16. Tabla sede Bucaramanga

SEDE BARRANQUILLA

Subred nacional 10.9.0.0

Subred local 192.168.12.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RBQUILLA	S0/0/0	10.9.0.2	255.255.0.0	N/A
	S0/0/1	192.168.12.34	255.255.255.224	N/A
RLBQUILLA	S0/0/0	192.168.12.33	255.255.255.224	N/A
	Fa0/0	192.168.12.1	255.255.255.224	N/A

Tabla 17. Tabla sede Barranquilla

SEDE VILLAVICENCIO

Subred nacional 10.10.0.0

Subred local 192.168.13.0

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RVICENCIO	S0/0/0	10.10.0.2	255.255.0.0	N/A
	S0/0/1	192.168.13.34	255.255.255.224	N/A
RLVICENCIO	S0/0/0	192.168.13.33	255.255.255.224	N/A
	Fa0/0	192.168.13.1	255.255.255.224	N/A

Tabla 18. Tabla sede Villavicencio

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
R NACIONAL	S0/0/0	200.21.85.93	255.255.240.0	N/A
	S0/0/1	192.168.3.98	255.255.255.252	N/A
	S0/1/0	10.1.0.9	255.255.255.252	N/A
	S0/1/1	10.1.0.13	255.255.255.252	N/A
	S0/2/0	10.1.0.1	255.255.255.252	N/A
	S0/2/1	10.1.0.5	255.255.255.252	N/A
	S0/3/0	10.1.0.17	255.255.255.252	N/A
	S0/3/1	10.1.0.21	255.255.255.252	N/A
	S1/0/0	10.1.0.25	255.255.255.252	N/A
	S1/0/1	10.1.0.29	255.255.255.252	N/A
	S1/1/0	10.1.0.33	255.255.255.252	N/A
	S1/1/1	10.1.0.37	255.255.255.252	N/A
	Fa0/1	192.168.2.34	255.255.255.252	N/A
R PISO 1 Y 2	Fa0/0	192.168.3.1	255.255.255.192	N/A
	Fa0/1	192.168.3.65	255.255.255.224	N/A
	S0/0/0	192.168.3.97	255.255.255.252	N/A
R PISO 3.	Fa0/0	192.168.2.1	255.255.255.224	N/A
	S0/0/1	192.168.3.33	255.255.255.252	N/A

2.2 DIRECCIONAMIENTO CON VLSM

SEDE PRINCIPAL PASTO

SUBRED DIRECCIONAMIENTO NACIONAL 10.0.0.0

SUBRED DIRECCIONAMIENTO LOCAL 192.168.0.0

SEDE BOGOTA

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RBTA	S0/0/0	10.1.0.2	255.255.255.252	N/A
	S0/0/1	192.168.4.34	255.255.255.252	N/A
RLBTA	S0/0/0	192.168.4.33	255.255.255.252	N/A
	Fa0/0	192.168.4.1	255.255.255.224	N/A

Tabla 19. Tabla sede Bogotá - VLSM

SEDE MEDELLIN

ProtocolRip V1	Interfaz	Direccion IP	Mascara de subred	Gateway por defecto
RMED	S0/0/0	10.1.0.6	255.255.255.252	N/A
	S0/0/1	192.168.5.34	255.255.255.252	N/A
RLMED	S0/0/0	192.168.5.33	255.255.255.252	N/A
	Fa0/0	192.168.5.1	255.255.255.224	N/A

Tabla 20. Tabla sede Medellín - VLSM

SEDE PEREIRA

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
RPEREIRA	S0/0/0	10.1.0.10	255.255.255.252	N/A
	S0/0/1	192.168.6.34	255.255.255.252	N/A
RLPEREIRA	S0/0/0	192.168.6.33	255.255.255.252	N/A
	Fa0/0	192.168.6.1	255.255.255.224	N/A

Tabla 21. Tabla sede Pereira - VLSM

SEDE CALI

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
RCALI	S0/0/0	10.1.0.14	255.255.255.252	N/A
	S0/0/1	192.168.7.34	255.255.255.252	N/A
RLCALI	S0/0/0	192.168.7.33	255.255.255.252	N/A
	Fa0/0	192.168.7.1	255.255.255.224	N/A

Tabla 22.Tabla sede Cali - VLSM

SEDE CARTAGENA

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
RCARTAGENA	S0/0/0	10.1.0.18	255.255.255.252	N/A
	S0/0/1	192.168.8.34	255.255.255.252	N/A
RLCARTAGENA	S0/0/0	192.168.8.33	255.255.255.252	N/A
	Fa0/0	192.168.8.1	255.255.255.224	N/A

Tabla 23. Tabla sede Cartagena - VLSM

SEDE IBAGUE

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
RIBAGUE	S0/0/0	10.1.0.22	255.255.255.252	N/A
	S0/0/1	192.168.9.34	255.255.255.252	N/A
RLIBAGUE	S0/0/0	192.168.9.33	255.255.255.252	N/A
	Fa0/0	192.168.9.1	255.255.255.224	N/A

Tabla 24.Tabla sede Ibagué - VLSM

SEDE CUCUTA

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
RCUCUTA	S0/0/0	10.1.0.26	255.255.255.252	N/A
	S0/0/1	192.168.10.34	255.255.255.252	N/A
RCUCUTA	S0/0/0	192.168.10.33	255.255.255.252	N/A
	Fa0/0	192.168.10.1	255.255.255.224	N/A

Tabla 25.Tabla sede Cúcuta - VLSM

SEDE BUCARAMANGA

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
RBMANGA	S0/0/0	10.1.0.30	255.255.255.252	N/A
	S0/0/1	192.168.11.34	255.255.255.252	N/A
RLBUMANGA	S0/0/0	192.168.11.33	255.255.255.252	N/A
	Fa0/0	192.168.11.1	255.255.255.224	N/A

Tabla 26. Tabla sede Bucaramanga - VLSM

SEDE BARRANQUILLA

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
RBQUILLA	S0/0/0	10.1.0.34	255.255.255.252	N/A
	S0/0/1	192.168.12.34	255.255.255.252	N/A
RLBQUILLA	S0/0/0	192.168.12.33	255.255.255.252	N/A
	Fa0/0	192.168.12.1	255.255.255.224	N/A

Tabla 27. Tabla sede Barranquilla - VLSM

SEDE VILLAVICENCIO

Protocolo Rip V1	Interfaz	Dirección IP	Mascara de subred	Gateway por defecto
RVICENCIO	S0/0/0	10.1.0.38	255.255.255.252	N/A
	S0/0/1	192.168.13.34	255.255.255.252	N/A
RLVICENCIO	S0/0/0	192.168.13.33	255.255.255.252	N/A
	Fa0/0	192.168.13.1	255.255.255.224	N/A

Tabla 28. Tabla sede Villavicencio - VLSM

2.3 CONFIGURACION DE LOS ROUTERS

Para presentar la configuración de los routers, se tendrá en cuenta de conexión nacional de la sede principal y los routers de la sede de Bogotá.

2.3.1 Configuración para sistema actual

Router Nacional Pasto

```
PASTO#show running-config
Building configuration...
```

```
Current configuration : 1436 bytes
```

```
!
version 12.4
no service password-encryption
!
hostname PASTO
!
!
!
!
!
ipssh version 1
!
!
interface FastEthernet0/0
noip address
duplex auto
speed auto
shutdown
!
interface FastEthernet0/1
ip address 192.168.3.130 255.255.255.224
duplex auto
speed auto
!
interface Serial0/0/0
ip address 200.21.85.93 255.255.255.240
!
interface Serial0/0/1
ip address 192.168.3.98 255.255.255.224
clock rate 64000
!
interface Serial0/1/0
ip address 10.3.0.1 255.255.0.0
clock rate 64000
!
interface Serial0/1/1
ip address 10.4.0.1 255.255.0.0
```

```
clock rate 64000
!  
interface Serial0/2/0  
ip address 10.1.0.1 255.255.0.0  
clock rate 64000  
!  
interface Serial0/2/1  
ip address 10.2.0.1 255.255.0.0  
clock rate 64000  
!  
interface Serial0/3/0  
ip address 10.5.0.1 255.255.0.0  
clock rate 64000  
!  
interface Serial0/3/1  
ip address 10.6.0.1 255.255.0.0  
clock rate 64000  
!  
interface Ethernet1/0  
noip address  
duplex auto  
speed auto  
shutdown  
!  
interface Serial1/0/0  
ip address 10.7.0.1 255.255.0.0  
clock rate 64000  
!  
interface Serial1/0/1  
ip address 10.8.0.1 255.255.0.0  
clock rate 64000  
!  
interface Serial1/1/0  
ip address 10.9.0.1 255.255.0.0  
clock rate 64000  
!  
interface Serial1/1/1  
ip address 10.10.0.1 255.255.0.0  
clock rate 64000  
!  
interface Vlan1  
noip address
```

```
shutdown
!  
router rip  
network 10.0.0.0  
network 192.168.3.0  
!  
ip classless  
ip route 0.0.0.0 0.0.0.0 Serial0/0/0  
!  
!  
!  
!  
!  
line con 0  
linevty 0 4  
login  
!  
!  
End
```

Router enlace nacional Bogotá

```
RBTA#show running-config  
Building configuration...
```

```
Current configuration : 547 bytes
```

```
!  
version 12.4  
no service password-encryption  
!  
hostname RBTA  
!  
!  
!  
!  
!  
ipssh version 1  
!  
!  
interface FastEthernet0/0  
noip address  
duplex auto
```

```
speed auto
shutdown
!
interface FastEthernet0/1
noip address
duplex auto
speed auto
shutdown
!
interface Serial0/0/0
ip address 10.1.0.2 255.255.0.0
!
interface Serial0/0/1
ip address 192.168.4.34 255.255.255.224
clock rate 64000
!
interface Vlan1
noip address
shutdown
!
router rip
network 10.0.0.0
network 192.168.4.0
!
ip classless
!
!
!
!
!
line con 0
linevty 0 4
login
!
!
End
```

Router enlace local Bogotá

```
RLBTA#show running-config
Building configuration...
```

Current configuration : 519 bytes

```
!  
version 12.4  
no service password-encryption  
!  
hostname RLBTA  
!  
!  
!  
!  
!  
ipssh version 1  
!  
!  
interface FastEthernet0/0  
ip address 192.168.4.1 255.255.255.224  
duplex auto  
speed auto  
!  
interface FastEthernet0/1  
noip address  
duplex auto  
speed auto  
shutdown  
!  
interface Serial0/0/0  
ip address 192.168.4.33 255.255.255.224  
!  
interface Serial0/0/1  
noip address  
shutdown  
!  
interface Vlan1  
noip address  
shutdown  
!  
router rip  
network 192.168.4.0  
!  
ip classless  
!  
!
```

```
!  
!  
!  
line con 0  
linevty 0 4  
login  
!  
!  
End
```

2.3.2 Configuración sistema con vlsm

Router Nacional Pasto

```
RPPAL# copy running-config star  
RPPAL# copy running-config startup-config  
Destination filename [startup-config]?  
Building configuration...  
[OK]  
RPPAL#showrunn  
RPPAL#show running-config  
Building configuration...
```

Current configuration : 2229 bytes

```
!  
version 12.4  
no service password-encryption  
!  
hostname RPPAL  
!  
!  
!  
!  
!  
ipssh version 1  
!  
!  
interface FastEthernet0/0  
noip address  
duplex auto  
speed auto
```

```
shutdown
!  
interface FastEthernet0/1  
ip address 192.168.2.34 255.255.255.252  
duplex auto  
speed auto  
!  
interface Serial0/0/0  
ip address 200.21.85.93 255.255.240.0  
!  
interface Serial0/0/1  
ip address 192.168.3.98 255.255.255.252  
clock rate 64000  
!  
interface Serial0/1/0  
ip address 10.1.0.9 255.255.255.252  
clock rate 64000  
!  
interface Serial0/1/1  
ip address 10.1.0.13 255.255.255.252  
clock rate 64000  
!  
interface Serial0/2/0  
ip address 10.1.0.1 255.255.255.252  
clock rate 64000  
!  
interface Serial0/2/1  
ip address 10.1.0.5 255.255.255.252  
clock rate 64000  
!  
interface Serial0/3/0  
ip address 10.1.0.17 255.255.255.252  
clock rate 64000  
!  
interface Serial0/3/1  
ip address 10.1.0.21 255.255.255.252  
clock rate 64000  
!  
interface Ethernet1/0  
no ip address  
duplex auto  
speed auto
```



```
shutdown
!  
interface Serial1/0/0  
ip address 10.1.0.25 255.255.255.252  
clock rate 64000  
!  
interface Serial1/0/1  
ip address 10.1.0.29 255.255.255.252  
clock rate 64000  
!  
interface Serial1/1/0  
ip address 10.1.0.33 255.255.255.252  
clock rate 64000  
!  
interface Serial1/1/1  
ip address 10.1.0.37 255.255.255.252  
clock rate 64000  
!  
interface Vlan1  
noip address  
shutdown  
!  
router eigrp 1  
network 192.168.3.0  
network 192.168.2.0  
auto-summary  
!  
router ospf 1  
log-adjacency-changes  
network 10.1.0.8 0.0.0.3 area 0  
network 10.1.0.12 0.0.0.3 area 0  
network 10.1.0.0 0.0.0.3 area 0  
network 10.1.0.4 0.0.0.3 area 0  
network 10.1.0.16 0.0.0.3 area 0  
network 10.1.0.20 0.0.0.3 area 0  
network 10.1.0.24 0.0.0.3 area 0  
network 10.1.0.28 0.0.0.3 area 0  
network 10.1.0.32 0.0.0.3 area 0  
network 10.1.0.36 0.0.0.3 area 0  
default-information originate  
!  
router rip
```

```
version 2
network 192.168.0.0
network 192.168.1.0
network 192.168.2.0
network 192.168.3.0
network 192.168.4.0
network 192.168.5.0
network 192.168.6.0
network 192.168.7.0
network 192.168.8.0
network 192.168.9.0
network 192.168.10.0
network 192.168.11.0
network 192.168.12.0
network 192.168.13.0
!
ip classless
ip route 0.0.0.0 0.0.0.0 Serial0/0/0
!
!
!
!
!
!
line con 0
linevty 0 4
login
!
!
End
```

Router Nacional Bogotá

```
BTA#show running-config
Building configuration...
```

```
Current configuration : 615 bytes
```

```
!
version 12.4
no service password-encryption
!
hostname BTA
!
```

```
!  
!  
!  
!  
ipssh version 1  
!  
!  
interface FastEthernet0/0  
noip address  
duplex auto  
speed auto  
shutdown  
!  
interface FastEthernet0/1  
noip address  
duplex auto  
speed auto  
shutdown  
!  
interface Serial0/0/0  
ip address 10.1.0.2 255.255.255.252  
!  
interface Serial0/0/1  
ip address 192.168.4.34 255.255.255.252  
clock rate 64000  
!  
interface Vlan1  
noip address  
shutdown  
!  
routerospf 1  
log-adjacency-changes  
network 10.1.0.0 0.0.0.3 area 0  
!  
router rip  
version 2  
network 192.168.4.0  
!  
ip classless  
!  
!  
!
```

```
!  
!  
line con 0  
linevty 0 4  
login  
!  
!  
end
```

Router Local Bogotá

```
Router#copy running-config startup-config  
Destination filename [startup-config]?  
Building configuration...  
[OK]  
Router#
```

Router con0 is now available

Press RETURN to get started.

```
Router>enable  
Router#configure terminal  
Enter configuration commands, one per line. End with CNTL/Z.  
Router(config)#hostname RLBTA  
RLBTA(config)#END  
%SYS-5-CONFIG_I: Configured from console by console  
RLBTA#copyrunn  
RLBTA#copy running-config  
% Incomplete command.  
RLBTA#copy running-configst  
RLBTA#copy running-config startup-config  
Destination filename [startup-config]?  
Building configuration...  
[OK]  
RLBTA#sowrunn  
RLBTA#show run  
RLBTA#show running-config  
Building configuration...
```

```
Current configuration : 568 bytes
!
version 12.4
no service password-encryption
!
hostname RLBTA
!
!
!
!
!
ipssh version 1
!
!
interface FastEthernet0/0
ip address 192.168.4.1 255.255.255.224
duplex auto
speed auto
!
interface FastEthernet0/1
noip address
duplex auto
speed auto
shutdown
!
interface Serial0/0/0
ip address 192.168.4.33 255.255.255.252
!
interface Serial0/0/1
noip address
shutdown
!
interface Vlan1
noip address
shutdown
!
router rip
version 2
network 192.168.4.0
!
ip classless
```

```
ip route 0.0.0.0 0.0.0.0 Serial0/0/0
!  
!  
!  
!  
!  
line con 0  
linevty 0 4  
login  
!  
!  
End
```

3. CONCLUSIONES

Con el desarrollo del caso de estudio de CCNA1 se adquirió muchas herramientas y conocimientos cuando se va a diseñar, implementar y estructurar alguna red. Teniendo en cuenta todos los imprevistos que se puedan presentar alcanzar su completa construcción con una conectividad eficiente. Hablando de imprevistos, si ellos suceden se hace necesario que se den en el diseño para poder hacer los cambios respectivos y no cuando ya la red este en funcionamiento, porque sería más complicado solucionarlo.

Gracias al desarrollo de las unidades de CCNA2, se complementó de manera específica una de las tantas ramas de la ingeniería de sistemas como lo es la comunicación de datos, a través de todos los procesos respectivos que ejecutan los equipos que la componen, para luego poder de una forma eficiente manipular la información de un lugar a otro a través de los respectivos enlaces. Todo el contenido de CCNA 2 nos dio las herramientas y conocimientos necesarios para saber la forma como se programan los principales equipos encargados del direccionamiento de los datos como lo son los routers.

BIBLIOGRAFIA

- NAVAS, Esteban. Algo de Linux. Internet: (enavas.blogspot.com/2009/02/minicom-acceso-switches-routers-por-el.html < <http://enavas.blogspot.com/2009/02/minicom-acceso-switches-routers-por-el.html> >)
- MÓDULO DE CURSO ACADÉMICO, Introducción a Networking y uso de algunas herramientas Software, Universidad Nacional Abierta y a Distancia – UNAD. Bogotá 2008.
- CISCO, CCNA2 exploración 4.0 conceptos y protocolos de enrutamiento, Universidad Nacional Abierta y a distancia UNAD, contenidos temáticos por unidades.
- URUEÑO LEÓN, Edsel Enrique. Direccionamiento IP. Internet: (www.monografias.com/trabajos29/direccionamiento-ip/direccionamiento-ip.shtml < <http://www.monografias.com/trabajos29/direccionamiento-ip/direccionamiento-ip.shtml> >).
- HACKHISPANO. Manual - División en subredes. Internet (www.hackhispano.com/foro/showthread.php?t=27277 <<http://www.hackhispano.com/foro/showthread.php?t=27277>>)